



Altair Panopticon™

PANOPTICON REAL TIME 2025.0-INSTALLATION AND REFERENCE GUIDE

TABLE OF CONTENTS

[1] INTRODUCTION	1
System Architecture	1
Visualization Server	2
Authentication and Authorization	3
Web Client	3
Containerized Deployment	3
Enterprise Deployment	4
Cloud Admin	4
Kubernetes Architecture for a Single Tenant / Namespace	5
Supported Ports, Protocols, and Services	6
Panopticon Online Documentation	6
Supported Connectors	6
System Requirements	7
System Hardware Requirements	9
[2] SETTING UP PANOPTICON REAL TIME	10
Panopticon Real Time Deployment Model	
Server Platforms	
Environment Promotion Options	
Before You Begin	
Configuring setenv.sh or setenv.bat	
Installing Panopticon Real Time	
Setting Up Panopticon Real Time on Linux	
Setting Up Panopticon Real Time on Windows	
The Welcome Page	21
Importing the Bundle of Example Workbooks	
Configuration of the Client Properties	
Map Tile Provider Customization	
Additional Information About the URL Format	36
Notes on using Google Maps or Bing Maps	37
Implications of Moving a Workbook to Another Server	
Consequences of File Editing Mistakes	
Licensing	
Using Altair Units License in Altair's License Server	
Using Managed Altair Units License Via Altair One	39
Proxy Server Configuration	
Managing File Handles	43
Identifying the Problem	44
Enabling Event Poll to Avoid False Warnings	45
Configuration Properties	45
Proxy	45
Apache HTTP Server	46



Load Balancer	47
Apache HTTP Server	47
Multiple Instances	48
Backup	49
Data Access and Caching	49
Content Repository	51
Server Cluster Configuration	51
Synchronizing Tokens	54
Cluster Shared Store: ZooKeeper	54
Exporting Legacy Files	55
Upgrading Panopticon Real Time	55
Content Migration	56
[3] AUTHENTICATION	59
Assign Roles	59
General Settings	60
Methods	61
Username and Password	61
LDAP	61
Active Directory	62
OAuth 2.0	62
SAML 2.0	63
Authentication Cookie	64
Security Headers	65
Migrate	65
Miscellaneous	66
Username and Password	66
LDAP	66
OAuth 2.0	67
SAML 2.0	68
[4] ADDITIONAL OR OPTIONAL STEPS	70
File Upload Size Limits Settings in Tomcat and Panopticon	70
Tomcat Memory Configuration for Linux	
Tomcat Memory Configuration for Windows	
Set Client Automatic Reconnection to the Server when Disconnected	
Automatic Logout of Users on Timeout to Save Unused Licenses	74
Setting the Transportation Protocol	
Panopticon Real Time Configurations for Email Send Outs and Alerts	
Font Installation Requirement for PDFs and Image export with CJK Characters	
Setting Server Properties Through the Environment Variables	
[5] ADVANCED SERVER DEPLOYMENTS	78
Lisage in SSI. Enabled Environments	78

Enabling SSL for Panopticon Real Time	78
Defining a TrustStore	80
[6] AUTHORIZATION	82
Secure Access	82
Creating Folders	82
Adding Groups and Users with Allowed Authorization	85
Adding Groups and Users with Denied Access	
Creating Subfolders	
Updating Folder or Subfolder Properties	
Downloading a Workbook	
Exporting Workbook or Folder Bundle	
Importing Workbooks Bundle	
Data Level Secure Access	96
[7] SYSTEM ADMINISTRATION	98
System Settings	99
View License Information	99
View Panopticon Real Time Information	101
View Plugin Subscriptions	102
Working with Caches	104
View Logs	
Scheduling Tasks	
Creating Task to Clear and Import Data Table to Data Store	
Creating Task to Import Data Table to Data Store	
Creating Task to Send CSV Data via Email	
Creating Task to Send an MS Excel File via Email	
Creating Task to Send an HTML Formatted Data via Email	
Creating Task to Send Image File via Email	
Creating Task to Send PDF File via Email	
Creating Task to Extract Data	_
Uploading a Scheduler Task	
Downloading a Scheduler Task	
Other Scheduler Tasks Operations	
Managing Panopticon Real Time Users	
Viewing Logged In Users	
Sorting Logged In Users	
Logging Out Users	
Logging Out All Users	
Logging Out Individual Users	
Refreshing the Logged In Users List	
Managing API Tokens	
Adding Custom Fonts	134
IOI CONNECTIVITY AND INTECDATION	400
[8] CONNECTIVITY AND INTEGRATION	136

Third Party Software Dependency Installation	138
Database	141
JDBC Driver Installation	141
JNDI Connection Details	141
Common Databases and their JNDI Configurations	143
R and Python Transform Support	143
R Integration	143
Python Integration with Pyro4	145
Python Integration with FastAPI	
Load Custom Data Plugins	148
[9] VIEWING AND MANAGING WORKBOOKS	149
Accessing Workbooks	149
Searching for Workbooks	151
Folders and Workbooks Display View	155
Sorting Workbooks	156
Creating Workbooks	157
Renaming Workbooks or Folders	157
Uploading Workbooks	158
Viewing Workbook History and Republishing	161
Moving Workbooks	165
Copying Workbooks	167
Sharing Workbooks	169
Parameter Value Passing Into the Web Client	170
Special Symbols to Pass Parameter Values Into the HTML5 Client	171
Replacing Parameter Values with HTTP Headers and Cookies	172
[10] DATA LIBRARY	176
Setting up Data Store	178
Caching	
[11] WEBHOOKS	180
Folders and Webhooks Display View	181
Searching for Webhooks	
Creating Webhooks	183
Webhooks Toolbar and Context Menu	186
Sorting Webhooks	187
Renaming a Webhook	188
Moving Webhooks	188
Copying Webhooks	189
Deleting Webhooks	190
Triggering Webhooks	191

[12] ALERTING					
Setting Up Alerts	192				
Working with Alerts					
Activating or Deactivating All Alerts					
Deleting Alerts					
Importing Alerts					
Exporting Alerts					
Viewing and Managing Alerts for Non-Administrator Users					
Sample Email Alerts					
Sample Web Client Alerts					
Adding Comments to an Alert					
Resolving an Alert					
Resolving All Open Alerts					
Delegating an Alert					
Sharing Alerts					
Stopping the Sharing of Alerts	220				
[13] GLOBAL PARAMETERS	222				
Adding Parameters	222				
Modifying Parameters	224				
Deleting Parameters	227				
Refresh Parameters	228				
Searching Parameters	228				
[14] MANAGING WORKBOOK THEMES	230				
Folders and Themes Display View	232				
Searching for Themes					
Creating a New Theme					
Defining the Default Style Settings of a Theme					
Defining the Custom Style Settings of a Theme					
Defining the Color Palettes Settings of a Theme					
Defining the General Color Settings of a Theme					
Defining the Editor Style Settings of a Theme					
Defining the Shape Palettes of a Theme					
Defining the Dashboard Templates of a Theme					
Themes Toolbar and Context Menu					
Sorting Themes					
Renaming a Theme					
Moving Themes					
Copying Themes					
Downloading Themes					
Uploading Themes					
Deleting Themes					
Dolouing Themes	202				

Color F	Palettes	263
	Importing a Color Palette	265
	Exporting Color Palette	266
	Creating a New Single Color Palette	267
	Creating a New Sign Color Palette	268
	Creating a New Text Color Palette	269
	Creating a Sequential or Diverging Numeric Color Palette	272
	Modifying Color Palettes	275
	Creating a Duplicate of a Color Palette	275
	Deleting Color Palettes	276
Shape	Palettes	277
	Creating a New Shape Palette	277
	Uploading a Shape Palette	279
	Downloading a Shape Palette	281
	Modifying Shape Palettes	281
	Creating a Duplicate of a Shape Palette	282
	Rearranging Shape Palettes	282
	Deleting Shape Palettes	283
	CLI: COMMAND UTILITIES FOR PANOPTICON REAL TIME	
	3	
J	1	
	Publishing a Workbook to Panopticon Real Time	
	Publishing a Workbook to a Folder	
	Publishing a Workbook Folder to Panopticon Real Time	
Version	Λ	
-	de	
. •	ify	
Exporto	datasource	289
Conver	rtpermissions	289
	eDatabaseToJDBC	
	ata	
Encryp	t	291
Decryp	yt	291
[16] RE	EST INTERFACE	293
API		293
Export	Data	
	CSV	294
	PDF	295
	Excel Workbook	297
Email [Data	298
	PDF	200

Image	300
[17] LOGGING/MONITORING	303
Server Logging	303
Configuring Server Logs	
Configuring Apache Tomcat Logs	304
Using java.util.logging (Default)	305
Audit Logging	308
Data Log Access in Dashboards	
Server Monitoring	309
Web Portal Integration	310
Setting the Server Metrics Publisher	310
Setting the Logging Level	312
[18] TROUBLESHOOTING	313
Resolving Installation Issues	313
Server Log	313
Pie Charts and Shapes Not Displaying Correctly in Chrome	314
Managed Altair Units License SSL Error	315
[19] KNOWN ISSUES	316
Out of Memory Exception	316
[20] PANOPTICON RESOURCES	317
[APPENDIX]	320
YAML	320
CORS	321
REST and Authentication	321
API Tokens	321
Basic Authentication	322
Session	322
Authentication Cookie	322
Properties: Panopticon	323

[1] INTRODUCTION


Altair® Panopticon™ is a product for data visualization, data analysis, data monitoring, and reporting. Users create dashboards, alerts, and reports by working in a browser-based environment with a point-and-click, drag-and-drop experience. A multitude of different data connectors are included in the product, enabling connectivity to local files, web URLs, databases, and streaming data sources. Panopticon supports blending data from separate data sources on-the-fly, in-memory. Tens of thousands of individual data points can be graphically visualized at once. The dashboard applications developed by users in a Designer role can subsequently benefit a larger group of users in Viewer role.

The product has access control settings for collections of dashboards, called workbooks, and data tables. Allow and Deny settings are available for capabilities **Read**, **Write**, and **Modify**, for individual users and for groups of users. In addition, Data Policies can be applied to data tables, which controls what parts of the data are accessible to different users, provided that the user is Allowed to Read the data table at all.


A Panopticon server will act as an automated data monitoring server when users create Alerts, which is a collection of data evaluation rules for a specific dashboard and data table. An alert that is triggered as a result of detecting data that matches the criteria, can send out a notification on screen, via email and as collaboration platform webhook message to for example Teams or Slack.

Panopticon has built-in task scheduling capabilities, which can be used for automatically distributing PDF report versions of dashboards via email, or sending data exports via email, or refreshing Data Store cached data tables.

SYSTEM ARCHITECTURE



Panopticon Visualization Server Architecture



Single Node Deployment (Non-containerized)

Panopticon consists of <u>server</u> and <u>client</u> parts. The server part is written in Java and runs as a Java Application on Apache Tomcat. The client part is written in HTML, CSS, JavaScript, and Angular.

Operating system requirements are listed <u>here</u> and in the <u>Technical Fact Sheet</u> documentation.

Hardware requirements, particularly for server-side hardware, are highly dependent on the deployment scale and the data complexity and data volumes. See System Hardware Requirements for more information.

Visualization Server

The server requires Java version 17 and Apache Tomcat 10.

User-created content such as workbooks with dashboards, data tables, and style themes are stored in repository directory in the form of small binary files which maintain a change log, like Git.

The server maintains an in-memory cache of data sets recently loaded from data sources, which avoids unnecessary repeated data loading from the data sources. The in-memory cache also assures scalability in the number of concurrent users since the same data set is cached in only one copy and a single data load from a data source will deliver data to a large number of users.

Panopticon supports the use of a third-party database as a Data Store, where data from any data connectors can be persistently cached, for example for the purpose of avoiding slow data loading due to badly performing data source. MonetDB is the recommended database for this purpose, but other JDBC compliant databases can also be used.

Panopticon has full support for containerized deployment with Docker, orchestration with Kubernetes and support for all major cloud platforms (AWS, Google, Azure, Oracle).

Panopticon has support for high-availability deployment of multiple Panopticon servers running in a cluster with a leader-followers principle, where automatic synchronization between cluster member servers assures the availability of identical content on each server. A sticky load balancer will be responsible for distributing users to the different cluster member servers.

Authentication and Authorization

Panopticon is designed for single sign-on (SSO) integration with existing identity providers in your organization. User credentials and groups of users are not managed inside Panopticon, instead, Panopticon makes use of the existing organization users and groups. Panopticon has out of the box support for LDAP, SAML, OAuth2, and Basic authentication.

Panopticon has three functional roles defined in the product: **Administrator**, **Designer**, and **Viewer**. Users and Groups defined in the Identity Provider (IdP) of the organization are mapped to these three functional roles as part of configuring the deployment. Any additional user groups/roles delivered by the IdP can also be used to define folder access permissions in the Panopticon content repository.


Administrators of Panopticon server will manage settings and configurations partly via a server administration web GUI, and partly in server-side configuration files. In addition, some operations can be effectuated through a command line tool Panopticon Command Line Interface (PCLI) and some operations can be effectuated by calling a REST API.

Web Client

The browser-based client part of Panopticon is built on the AngularJS web development framework. Officially supported browsers are Safari and Google Chrome, while up-to-date versions of Firefox and MS Edge can also be expected to be compatible with Panopticon.

The client software can be customized in terms of style and look and feel on two levels: The client can be modified by making server-side changes to achieve custom branding or white-labelling. The client look-and-feel can be changed by creating and applying a custom Style Theme, which includes settings for background and foreground colors, margins, padding, border widths, font settings, color palettes, and more. Custom fonts can also be added to the server.

CONTAINERIZED DEPLOYMENT




Containerized Deployment of Docker Compose

Panopticon can be obtained as a Docker Compose package consisting of four containers where the images will be pulled from Altair's image repository. See the detailed documentation to set up the Docker Compose package.

Panopticon with Docker Compose is meant for quick and easy product evaluation and testing, and not for production grade implementation.

ENTERPRISE DEPLOYMENT



Enterprise Deployment of Kubernetes

The Kubernetes deployment of Panopticon is similar in structure to the Docker Compose deployment, with an added Namespace abstraction layer.

Each namespace represents a completely isolated Panopticon tenant deployment and can be configured to meet specific requirements.

The configuration of the pods running in each namespace is controlled by a Helm Charts package.


Cloud Admin

The Cloud Admin app allows self-service creation, updating, deletion, backup, and restoration of Panopticon tenant instances. It is deployed as a namespace alongside the other Panopticon tenants. However, while Panopticon tenants can be configured for any type of authentication (LDAP, SAML, OAuth, Basic), the Cloud Admin app has fixed "superuser" authentication to keep it separate from application users.

Cloud Admin can be configured to operate in two modes:

Mode	Description	
Cloud Admin	Manage multiple tenants.Creation of new tenants is allowed.	
Tenant Admin	Manage one single tenant.Creation of new tenants is not allowed.	

Kubernetes Architecture for a Single Tenant / Namespace



Kubernetes Architecture in Detail for a Single Tenant /Namespace

The diagram above illustrates the various elements making up a single tenant deployment of Panopticon. It is designed to be scalable, secure, and performant using the industry-standard horizontal and vertical scaling approaches.

- Ingress performs the functions of Load balancing and SSL termination and allows external traffic to reach the Panopticon server
- ☐ The **panoviz** service directs all incoming traffic to the pods running Tomcat and Panopticon application deployed to them
- ☐ The Rserve, Python, and MonetDB workloads are not exposed to the external world and are only accessible to the Panopticon application
- All of the stateful sets support local storage like GP2, Standard, Azure-disk, etc. to store local data and nfs storage for shared content amongst the replicas
- All of the configurations that can be modified are modeled using Config maps and can be edited or viewed at any time for better maintenance

SUPPORTED PORTS, PROTOCOLS, AND SERVICES

Services	Description	Protocol	Port
Panoviz	Panopticon Visualization Server instance.	HTTP, HTTPS, WebSocket	8080, 80, 8443, 443
Panoviz	Email server communication for alert notifications, scheduled email reports	SMTP/SMTPs	25, 465, 587
Panoviz (optional)	SSO integration	LDAP /LDAPs	389, 636
Panoviz	Data connections (e.g., databases, message buses)	Various	Various ports depending on data source
MonetDB (optional)	MonetDB database instance backing the Data Store feature	JDBC	50000 (configurable)
Python FastAPI (optional)	Python script execution backend.	REST	9090 (configurable)
Rserve (optional)	R script execution backend	Rserve	6311 (configurable)

Panopticon Online Documentation

Horo	ara	th a	مالمنا	+-	tha	product's	dooumonte	ation.
пеге	are	uie	IIIIKS	ιΟ	uie	product S	documenta	สแบบ.

- Panopticon Online Documentation
- □ Technical Fact Sheet
- Web Authoring Quick Start Guide
- Server Installation and Reference Guide (PDF, HTML)
- Docker Compose Package Installation Guide (<u>PDF</u>, <u>HTML</u>)
- Web Authoring Guide (<u>PDF</u>, <u>HTML</u>)
- Client User Guide (<u>PDF</u>, <u>HTML</u>)
- White Labeling Guide

Supported Connectors

Panopticon supports the following data connectors:

- General Connectivity: MS Excel, Text, XML, JSON, Restful Web services, JDBC Databases
- ☐ **Big Data**: Cassandra, Elasticsearch 7.x, KsqlDB, MongoDB
- **Event Processing**: Kx kdb+Tick, OneMarketData OneTick CEP, Tibco Streambase, Tibco LiveView, Panopticon Streams

	Messaging Streaming: Apache/Confluent Kafka, JMS (e.g., ActiveMQ), Solace, RabbitMQ, WebSocket, JMX, Google Cloud Pub/Sub, MQTT						
	☐ Tick Data: OneMarketData OneTick, Kx kdb+, InfluxDB 1.x						
	□ Custom code data connections, transforms, and ML model scoring: Python, R, and REST service calls						
		con Real Time includes a Panopticon bundle file of example workbooks (Examples.exz). To use poks, the <u>bundle file must be imported</u> into the server after the server installation.					
	NOTE	 Beginning with version 17.1, MS Access, Valo, Apache Qpid, Valo Streaming, Ultra Messaging Streams, and OData connectors are deprecated. Beginning with version 16.2, DataDirect based connectors, along with Vertica, are deprecated. The Database connector or JDBC Database connector should be used. Existing workbooks will continue to operate, but connectivity will need to be migrated for subsequent releases. 					
Pan	opticon Real Ti	REQUIREMENTS me is supported on these operating systems:					
Linu		s the following distributions and versions:					
	Red Hat Linux	s (RHEL) 9.4					
	Debian 11						
	□ Ubuntu 22.04 LTS						
	Fedora 40						
Wind	dows operating	systems – For Evaluation, Development, and Testing Environments Only					
□ Windows 10 or higher (64-bit)							
	Windows Serv	ver 2012 or higher (64-bit)					
Pan	opticon Real Ti	me also requires:					
	Oracle Java S	E 17 and Open JDK 17					
	NOTE	See Java documentation about setting up the JAVA_HOME environment					

variable in your system.

See Required Java Option Settings with Java 17 for the required additional configuration to load Apache Arrow files and to be able to use Arrow serialization with Python.

Apache Tomcat 10

NOTE

When running on Windows instead of Linux, it is recommended to use the zip distribution of Apache Tomcat for Windows rather than the Windows Service Installer. This is because the zip distribution will let you run Apache Tomcat without any dependency on the Windows service manager, and management of the Apache Tomcat server will conform more with how it is done on Linux.

NOTE

Starting with Tomcat 9, Debian Linux implements a security policy which puts a harder default restriction on which folders a Tomcat 9 web application can write to.

The change is described in full detail here:

https://salsa.debian.org/java-team/tomcat9/-/commit/3ca5cbdc2f970470341926354f210dff032fc5f3

Quoting from the release notes:

 Tomcat is sandboxed by systemd and only has write access to the following directories:

Directory	Actual Directory
/var/lib/tomcat9/conf/Catalina	/etc/tomcat9/Catalina
/var/lib/tomcat9/logs	/var/log/tomcat9
/var/lib/tomcat9/webapps	
/var/lib/tomcat9/work	/var/cache/tomcat9

• If write access to other directories is required, override the service settings. This is done by creating an override.conf file in

/etc/systemd/system/tomcat9.service.d/ containing:

[Service]

ReadWritePaths=/path/to/the/directory/

Ensure to restart the service afterward with:

- o systemctl daemon-reload
- systemctl restart tomcat9


Panopticon Real Time is supported for deployment on the following cloud providers:

Amazon Web Services (AWS)
Microsoft Azure
Google Cloud Platform
Oracle Cloud
Containerized deployment with Docker Linux containers is also supported.

Sup	oported br	owsers include the latest version of:
	Google	Chrome
	Safari	
	NO	Panopticon Real Time requires administrative privileges during installation. Administrative privileges are not required after installation is complete.
Sy	stem F	lardware Requirements
De	velopme	ent / Test
	1 x Dual	Core CPU (Hyper Threaded to 4 Cores/Threads)
	8GB RA	М
	4GB Dis	k (Available)
	In Memo	ory Caching limited to available Server RAM
Sm	nall Scal	e Deployment
	1 x Qua	d Core CPU Or Equivalent (Hyper Threaded to 8 Cores/Threads)
	16GB R	AM
	4GB Dis	k (Available)
	In Memo	ory Caching limited to available Server RAM
Me	dium So	cale Deployment
	4 x Qua	d Core CPU Or Equivalent (Hyper Threaded to 32 Cores/Threads)
	32GB R	AM
	4GB Dis	k (Available)
	In Memo	ory Caching limited to available Server RAM
Laı	rge Scal	e Deployment
	8 x Qua	d Core CPU Or Equivalent (Hyper Threaded to 64 Cores/Threads)
	64GB R	AM
	4GB Dis	k (Available)
	In Mama	nn Caching limited to available Server RAM

[2] SETTING UP PANOPTICON REAL TIME

PANOPTICON REAL TIME DEPLOYMENT MODEL



Full scale Panopticon Real Time deployment

Panopticon Real Time is deployed and hosted on an internal network. The server can be accessed internally and/or externally from the internet. Upon allowing access to the server from the internet it is recommended to have a proxy and firewall in front of the server.

Panopticon Real Time exposes web services from both a SOAP interface and a REST interface. These interfaces are used by the Web client but can also be used to execute functionality directly on the server such as by batch jobs.

Workbook access is secured through the underlying application Panopticon Real Time security model, such as authentication and configuration of directories in Tomcat.

Furthermore, Panopticon Real Time is capable of the following features:

- □ SSO Support through SAML
- JDBC / JNDI Data Sources
- JMX Monitoring

Server Platforms

Panopticon Real Time consist of multiple components such as the following:

Components	Description
Panopticon Real Time	Formerly named Panopticon Visualization Server, responsible for managing all the published workbooks and all the resources that go with them. It is also responsible for authorization, data connections, transformations, scheduled tasks, report generation, alerting, etc.
Panopticon Streams	Processing of data streams for real-time visualization in dashboards.
Web Client	Graphical interface for administration of the server and for creation and design of dashboard applications.

See Installation for more information.

ENVIRONMENT PROMOTION OPTIONS

You may need to set up multiple environments for Panopticon. For example, you may wish to set up your system to support one of the following migration paths:

- ☐ Staging → Production
- □ Development → User Acceptance Testing → Production

The primary complication when promoting workbooks between environments is access to data repositories since you may wish to use separate data repositories for each environment. If you require different data repositories in each environment, use JNDI or global parameters. These abstract the location of the data repository from the workbook.

BEFORE YOU BEGIN

Before you begin the installation of Panopticon Real Time, you may need to:

- Verify that your system meets the system requirements
- Configure setenv.sh (for Linux) or setenv.bat (for Windows)

IMPORTANT

Before installing Panopticon on Tomcat, you must start Tomcat at least once. Make sure Tomcat is stopped before starting the installation of Panopticon.

Configuring setenv.sh or setenv.bat

Configuration is done by adding a setting in the setenv.sh (for Linux) or setenv.bat (for Windows) in the setenv.bat (file does not exist, you must create it.

Windows

Point out the Java installation to use.

Add the following lines:

```
set JAVA_HOME=JDK_home\[JDK folder]
set JRE HOME= JDK home\[JDK folder]
```

Set the UTF-8 character encoding.

Add the following line:

```
set JAVA OPTS=%JAVA OPTS% -Dfile.encoding=UTF-8
```

Enable Arrow Serialization.

With Java 17, this setting is necessary for loading Apache Arrow files and for using Arrow serialization with Python. Add the following line:

```
set JAVA OPTS=%JAVA OPTS% --add-opens java.base/java.nio=ALL-UNNAMED
```

Example

```
set JAVA_HOME=C:\Program Files\RedHat\java-17-openjdk-17.0.10.0.7-2 set JRE_HOME=C:\Program Files\RedHat\java-17-openjdk-17.0.10.0.7-2 set JAVA_OPTS=%JAVA_OPTS% -Dfile.encoding=UTF-8 set JAVA_OPTS=%JAVA_OPTS% --add-opens java.base/java.nio=ALL-UNNAMED
```

Finally, save the file setenv.bat.

For further details, see the Apache Tomcat 10 documentation.

Linux

Point out the Java installation to use.

Add the following lines:

```
JAVA_HOME=/path/to/jvm/version
JRE_HOME=/path/to/jvm/version
```

Set the UTF-8 character encoding.

Add the following line:

```
JAVA OPTS="$JAVA OPTS -Dfile.encoding=UTF-8"
```

Enable Arrow Serialization.

With Java 17, this setting is necessary for loading Apache Arrow files and for using Arrow serialization with Python. Add the following line:

```
JAVA OPTS="$JAVA OPTS --add-opens java.base/java.nio=ALL-UNNAMED"
```

Example

```
JAVA_HOME=/usr/lib/jvm/java-1.17.0-openjdk-amd64

JRE_HOME=/usr/lib/jvm/java-1.17.0-openjdk-amd64

JAVA_OPTS="$JAVA_OPTS -Dfile.encoding=UTF-8"

JAVA_OPTS="$JAVA_OPTS --add-opens_java.base/java.nio=ALL-UNNAMED"
```

Finally, save the file setenv.sh.

For further details, see the Apache Tomcat 10 documentation.

NOTE

If you don't have the correct Java Options setting for Arrow, you will see the following error message when trying to load an Arrow file:"

Handler dispatch failed:
java.lang.ExceptionInInitializerError

The Tomcat console will log:

java.lang.RuntimeException: Failed to initialize
MemoryUtil. Was Java started with --addopens=java.base/java.nio=ALL-UNNAMED? (See
https://arrow.apache.org/docs/java/install.html)

<etc..>

Caused by:

java.lang.reflect.InaccessibleObjectException: Unable to make field long java.nio.Buffer.address accessible: module java.base does not "opens java.nio" to unnamed module @2322f814

INSTALLING PANOPTICON REAL TIME

This section provides instructions on how to install Panopticon Real Time on Linux or Windows.

NOTE

If you need to upgrade your previously installed Panopticon Real Time, proceed to the $\underline{\mathsf{Upgrade}}$ section.

Setting Up Panopticon Real Time on Linux

Follow the steps and guidelines below to install Panopticon Real Time on Linux.

NOTE

Linux is a recommended operating system for product implementation.

Steps:

1. Extract the contents of AltairPanopticonVisualizationServerWAR_<version number>.zip file to a new location.

This .ZIP file will contain the following folder and files:

- pcli.zip
- python_integration folder
- tomcat-users_example.xml
- panopticon.xml
- panopticon.war
- PanopticonJNDIDataSourceFactory.jar
- Examples.exz
- CustomMessageParserExample.zip
- Elastic_5X_Dependencies.zip
- Elastic_6X_Dependencies.zip
- Elastic_7X_Dependencies.zip
- Panopticon Web Authoring Quick Start Guide
- Panopticon Web Authoring Guide
- Panopticon Real Time Installation and Reference Guide
- User_License.rtf
- 2. Make sure that your Tomcat server is stopped.
- 3. Create the AppData folder (i.e., /etc/panopticon/appdata) and ensure that the user account Local Service running Tomcat has read/write and execute permissions to this folder.
- 4. Copy the file panopticon.xml from the .ZIP file and place it in the Tomcat config folder (/tomcat home/conf/Catalina/localhost).
- 5. Edit the Environment value property to the path where you want to keep Panopticon server content, for example:

NOTE

Instead of setting the path of the environment variable
 PanopticonAppData on the panopticon.xml file, you can do so on the
 System Environment Variables. For example:

Variable	New Value
PanopticonAppData	/etc/panopticon/panopticondata

• If the directory path is set in both an environment variable and in the panopticon.xml file, the value set in the XML file will take precedence.

- 6. Copy the panopticon.war file into the Tomcat webapps folder (/tomcat home/webapps).
- 7. For a basic installation using the Tomcat inbuilt XML file user directory, copy the provided tomcatusers example.xml and overwrite the existing tomcat-users.xml file which is available in the Tomcat config folder (/tomcat home/conf).

The provided tomcat-users example.xml contains the following roles and users:

```
<role rolename="user"/>
<role rolename="designer"/>
<role rolename="admin"/>
<user username="viewer" password="viewer" roles="user" />
<user username="designer" password="designer" roles="user,designer" />
<user username="admin" password="admin" roles="user,admin"/>
<user username="su" password="su" roles="user,designer,admin"/>
```

- **IMPORTANT** Before proceeding to step 7, ensure the Tomcat temp folder (e.g., (/tomcat home/temp) is available.
 - You can opt to choose a different temp folder with the CATALINA_TMPDIR environment variable. For example:

Variable	Value
CATALINA_TMPDIR	/tomcat_home/dev/temp

8. Start Tomcat to deploy the panopticon.war file.

The server initializes the AppData directory with an empty content repository and empty subdirectories for other types of data. The Panopticon.properties file is created with the default server properties.

- 9. Specify the license type that will be used. Use any of the following license types:
 - Volume License file (PanopticonLicense.xml) that must be copied to the designated AppData folder.
 - Altair Units license. Refer to Using Altair Units License in Altair's License Server for more information.
 - Managed Altair Units license. Refer to Using Managed Altair Units License Via Altair One for more information
- 10. Increase the Java heap size of Tomcat.
- 11. You can also opt to install Java data connector's dependencies.
- 12. You should now be able to log on to Panopticon Real Time using the following:

```
[Host Name]:[Port]/[Name of your application]
```

For example:

```
http://localhost:8080/panopticon
```

The more advanced configuration options are also discussed in this document.

NOTE

Python integration for data connectivity via Python and transforms using Python is achieved in either of these two ways:

- With FastAPI Refer to <u>Python Integration with FastAPI</u> for more information.
- With Pyro4 Refer to Python Integration with Pyro4 for more information.

Setting Up Panopticon Real Time on Windows

NOTE

You should use the Windows zip distribution of Apache Tomcat for Windows rather than the Windows Service Installer.

Follow the steps and guidelines below to install Panopticon Real Time on Windows.

Steps:

1. Extract the contents of AltairPanopticonVisualizationServerWAR_<version number>.zip file to a new location.

This .ZIP file will contain the following folder and files:

- pcli.zip
- python_integration folder
- tomcat-users_example.xml
- panopticon.xml
- panopticon.war
- PanopticonJNDIDataSourceFactory.jar
- Examples.exz
- CustomMessageParserExample.zip
- Elastic_5X_Dependencies.zip
- Elastic_6X_Dependencies.zip
- Elastic_7X_Dependencies.zip
- Panopticon Web Authoring Quick Start Guide
- Panopticon Web Authoring Guide
- Panopticon Real Time Installation and Reference Guide
- User_License.rtf
- 2. Make sure that your Tomcat server is stopped.
- 3. Create the AppData folder (i.e., panopticondata) and ensure that the user account Local Service running Tomcat has read/write and execute permissions to this folder.

Example: C:\panopticondata

4. Copy the extracted panopticon.xml file into the Tomcat config folder. This file contains the following information:

5. Edit the Environment value property to the path where you want to keep Panopticon server content, for example:

NOTE

Instead of setting the path of the environment variable
PanopticonAppData on the panopticon.xml file, you can do so on the
System Environment Variables. For example:

Variable	New Value
PanopticonAppData	C:\panopdata

- If the directory path is set in both an environment variable and in the panoption.xml file, the value set in the XML file will take precedence.
- 6. Copy the panopticon.war file into the Tomcat webapps folder (\Apache Software Foundation\Tomcat 10.0\webapps).
- 7. For a basic install using the Tomcat inbuilt XML file user directory, copy the provided tomcatusers_example.xml and overwrite the existing tomcat-users.xml file which is available in the Tomcat config folder (\Apache Software Foundation\Tomcat 10.0\conf).

The provided tomcat-users example.xml contains the following roles and users:

```
<role rolename="user"/>
<role rolename="designer"/>
<role rolename="admin"/>
<user username="viewer" password="viewer" roles="user" />
<user username="designer" password="designer" roles="user,designer" />
<user username="admin" password="admin" roles="user,admin"/>
<user username="su" password="su" roles="user,admin"/>
<user username="su" password="su" roles="user,designer,admin"/>
```

8. You can also opt to install Java data connector's dependencies, and JDBC driver JAR files as required.


IMPORTANT •

- Before proceeding to step 9, ensure the Tomcat temp folder (e.g., (\Apache Software Foundation\Tomcat 10.0\temp) is available.
- You can opt to choose a different temp folder with the CATALINA_TMPDIR environment variable. For example:

Variable	Value
CATALINA_TMPDIR	C:\tomcat\dev\temp

9. Start Tomcat to deploy the .war file.

The panopticon folder is extracted in the Tomcat webapps folder:




The server initializes the AppData directory with an empty content repository and empty subdirectories for other types of data. The Panopticon.properties file is created with the default server properties.

- 10. Specify the license type that will be used. Use any of the following license types:
 - Volume License file (PanopticonLicense.xml) that must be copied to the designated AppData folder.
 - Altair Units license. Refer to <u>Using Altair Units License in Altair's License Server</u> for more information.
 - Managed Altair Units license. Refer to <u>Using Managed Altair Units License Via Altair One</u> for more information.
- 11. Increase the <u>Java heap size of Tomcat</u>.
- 12. You should now be able to log on to Panopticon Real Time using the following:

[Host Name]:[Port]/[Name of your application]

For example:

http://localhost:8080/panopticon



The more advanced configuration options are also discussed in this document.

NOTE

To support Python Transform, the following files are included in the installation zip file:


- start_Python_connectivity.sh
- start_Python_connectivity.bat
- pyro.py

Refer to Python Integration with Pyro4 for more information.

NOTE


Panopticon Real Time supports different user roles. To have full access to all the services, the user is required to have ADMINISTRATOR and DESIGNER roles.

For example, logging on using the ADMINISTRATOR role added in step 6 (i.e., admin/admin), will display:



All of the available user specific folders in the <u>authentication</u> method used are displayed.


However, logging on with a DESIGNER role (i.e., designer/designer) will only display:



The allowed features available for the DESIGNER role is extensively discussed in the <u>Web Authoring Guide</u>.

The Welcome Page

The *Welcome* page is the first screen that displays when you log on to Panopticon Real Time. This page can also be accessed by clicking the **Altair Panopticon** logo on the header.




From this page you can:

- ☐ Click See All Workbooks to go to the Workbooks page
- □ Open recently viewed workbooks
- Explore workbooks available in your organization
- Open the Analyst User Guide
- □ View online documentation and help

⇒ See All Workbooks

If there are no recently viewed workbooks, header.

is displayed parallel to the Getting Started




Importing the Bundle of Example Workbooks

The AltairPanopticonVisualizationServerWAR_<version number>.zip file includes the bundle file of the example workbooks and their associated data files (Examples.exz).


Follow the instructions below to import this bundle to Panopticon Real Time.

Steps:

 On the Workbooks and Folders Summary page, right-click on a folder and select Import Bundle on the context menu.




The Import Bundle dialog displays.



- 2. To import the bundle, you can either:
 - Drag it from your desktop and drop on the dialog, or
 - Click Choose Bundle to Import and select one on the Open dialog that displays.

The name of the selected bundle is displayed on the dialog box.



3. Select the Keep Folder Structure checkbox.

This means the exported folder structure is maintained when uploading the bundle. If the folders do not exist on the server, they will be created.

To replace an existing workbook, select the **Replace existing workbook** checkbox.



Click 5.

The example workbooks that you can view and explore are imported.

CONFIGURATION OF THE CLIENT PROPERTIES

Starting with version 2020.1, Panopticon Real Time generates JSON configuration files in the JavaScriptConfiguration directory of the AppData folder (i.e., /etc/panopticon/appdata).

```
NOTE
              In the JSON files, a dot in the name (e.g., name1.name2) is used to denote a
              nested object structure:
                "name1": {
                   "name2": ...
              }
```

The default content of the admin.json file has the following objects/names:

```
{
  "baseUrl" : ".",
  "hideAuthenticationButton" : false,
}
```

In the admin.json file, you can control the configuration of the following objects/names:

Object/Name	automaticReconnectOnServerDisconnect
Description	If set to true , the real time connection (WebSocket or long polling) to the Panopticon server will be automatically reconnected if it is disconnected.
Default Value	false
Required	No
Object/Name	baseUrl
Description	Location of Panopticon Real Time.
Default Value	"."
Required	Yes
Object/Name	dataLoading.transport
Description	Controls which transport should be used when viewing log from the server. Valid values are "websocket" and "long-polling". If configured to "websocket", but the WebSocket connection fails, then the web client will automatically fall back to "long-polling".
Default Value	"websocket"
Required	No
Object/Name	hideAuthenticationButton
Description	Boolean. Hides the login and logout buttons.
Default Value	false
Required	No
Object/Name	localization.defaultLocale
Description	Locale used if the browser locale is not supported, or if the useBrowserLocale is set to false.
Default Value	"en-US"
Required	No
Object/Name	localization.fallbackLocale
Description	Locale used if a resource string is missing from the locale in use. Should be specified if localization.defaultLocale is specified.
Default Value	value of localization.defaultLocale
Required	No

611 481	
Object/Name	localization.useBrowserLocale
Description	Boolean. If set to true , the browser navigator.language, navigator.userLanguage on IE11, controls the localization of the UI. Not all languages are supported.
Default Value	true
Required	No
Object/Name	localizationOverride
Description	Nested object with resource strings per language. Used to customize resource strings.
Default Value	
Required	No
Object/Name	logLevel
Description	Controls which types of logs Panopticon will write to the browser dev console. Valid values are: "trace", "debug", "info", "warn", "error" and "silent".
Default Value	"info"
Required	No
Object/Name	workbookUrl
Description	Location of the workbook application. NOTE: The workbookUrl property should reflect the actual location of the workbook application, but it doesn't rename or change the location of said application.
Default Value	"workbook"
Required	Yes
Object/Name	dataLoading.connectTimeout
Description	Controls the timeout used, in milliseconds, when opening the data loading connection to the server.
Default Value	10000
Required	No
Object/Name	showFileUploadUI
Object/Name Description	showFileUploadUI Controls the visibility of UI that is used to upload a file to the server.
•	-
Description	Controls the visibility of UI that is used to upload a file to the server.
Description Default Value	Controls the visibility of UI that is used to upload a file to the server. true
Description Default Value Required	Controls the visibility of UI that is used to upload a file to the server. true No
Description Default Value Required Object/Name	Controls the visibility of UI that is used to upload a file to the server. true No showLinkToFileUI Controls the visibility of UI that is used to specify a data file on the server local file system as a data source. Per default, this flag is automatically inserted into the client
Description Default Value Required Object/Name Description	Controls the visibility of UI that is used to upload a file to the server. true No showLinkToFileUI Controls the visibility of UI that is used to specify a data file on the server local file system as a data source. Per default, this flag is automatically inserted into the client configuration at runtime.
Description Default Value Required Object/Name Description Default Value	Controls the visibility of UI that is used to upload a file to the server. true No showLinkToFileUI Controls the visibility of UI that is used to specify a data file on the server local file system as a data source. Per default, this flag is automatically inserted into the client configuration at runtime. true

Description	Controls only visibility of Data Library tab for viewer role.
Default Value	true
Required	No
Object/Name	visibleViewerTabs.webhooks
Description	Controls only visibility of Webhooks tab for viewer role.
Default Value	true
Required	No
Object/Name	visibleViewerTabs.alerts
Description	Controls only visibility of Alerts tab for viewer role.
Default Value	false
Required	No
Object/Name	visibleViewerTabs.parameters
Description	Controls only visibility of Parameters tab for viewer role.
Default Value	false
Required	No
Object/Name	visibleViewerTabs.themes
Description	Controls only visibility of Themes tab for viewer role.
Default Value	False
Required	No
Object/Name	visibleViewerTabs.system
Description	Controls only visibility of System tab for viewer role.
Default Value	false
Required	No
Object/Name	visibleDesignerTabs.datatables
Description	Controls only visibility of Data Library tab for designer role.
Default Value	true
Required	No
Object/Name	visibleDesignerTabs.webhooks
Description	Controls only visibility of Webhooks tab for designer role.
Default Value	true
Required	No
Object/Name	visibleDesignerTabs.alerts
Description	Controls only visibility of Alerts tab for designer role.

Default Value	true
Required	No
Object/Name	visibleDesignerTabs.parameters
Description	Controls only visibility of Parameters tab for designer role.
Default Value	true
Required	No
Object/Name	visibleDesignerTabs.themes
Description	Controls only visibility of Themes tab for designer role.
Default Value	true
Required	No
Object/Name	visibleDesignerTabs.system
Description	Controls only visibility of System tab for designer role.
Default Value	false
Required	No
Object/Name	maxrowcount
Description	Controls the maximum number of rows a table can return.
Default Value	100000
Required	No
Object/Name	preventDataLoadOnMaxRowCountExceeded
Description	Controls whether an exception is raised when number of rows from the data table exceeds maxRowCount or should the rows be truncated.
Default Value	true
Required	No
Object/Name	connectors.showLegacyButton
Description	Controls the visibility of the Show Legacy Connectors switch button in the select connector panel. Used to show/hide legacy connectors.
Default Value	true
Required	No
Object/Name	connectors.legacyVisible
Description	Default value of Show Legacy Connectors switch button in select connector panel.
Default Value	false
Required	No

The default content of the workbook.json file has the following objects/names:

```
{
  "baseUrl" : "..",
  "forceClientSelectionHandling" : true,
  "startUrl" : "../",
  "subscriptionCompression" : true,
  "dataLoading" : {
     "transport" : "websocket"
  },
  "webGlEnabled" : true,
  "pdfMultiplePagesEnabled" : true
}
```

In the workbook.json file, you can control the configuration of the following objects/names:

Object/Name	baseUrl	
Description	Location of Panopticon Real Time.	
Default Value	""	
Required	Yes	
Object/Name	localization.useBrowserLocale	
Description	Boolean. If set to true, the browser navigator.language, navigator.userLanguage on IE11, controls the localization of the UI. Not all languages are supported.	
Default Value	true	
Required	No	
Object/Name	localization.defaultLocale	
Description	Locale used if the browser locale is not supported, or if useBrowserLocale is set to false.	
Default Value	"en-US"	
Required	No	
Object/Name	localization.fallbackLocale	
Description	Locale used if a resource string is missing from the locale in use. Should be specified if localization.defaultLocale is specified.	
Default Value	value of localization.defaultLocale	
Required	No	
Object/Name	localizationOverride	
Description	Nested object with resource strings per language. Used to customize resource strings.	
Default Value		
Required	No	

Object/Name	logLevel	
Description	Controls which types of logs Panopticon will write to the browser dev console. Valid values are: "trace", "debug", "info", "warn", "error" and "silent".	
Default Value	"info"	
Required	No	
Object/Name	disableExternalHelpText	
Description	Disables the browser dev console splash screen.	
Default Value	false	
Required	No	
Object/Name	theme	
Description	Name of the default theme for all workbooks. Per default, the first theme available is picked as the default theme.	
Default Value		
Required	No	
Object/Name	allowOrigin	
Description	A comma separated list of allow origins, used by the Panopticon POST message API.	
Default Value		
Required	No	
Object/Name	automaticReconnectOnServerDisconnect	
Description	If set to true , the real time connection (WebSocket or long polling) to the Panopticon server will be automatically reconnected if it is disconnected.	
Default Value	false	
Required	No	
Object/Name	alwaysHideNonInteractiveParametersInDialog	
Description	Hides parameters that are not interactive when displaying the interactive parameter dialog.	
Default Value	false	
Required	No	
Object/Name	enableDevicePixelRatioCanvasScaling	
Description	Enable or disable handling of device pixel ratio for 2D visualizations.	
Default Value	true	
Required	No	
Object/Name	staleStateTimeout	
Description	Time (in milliseconds) that controls how fast the "stale data" overlay should be rendered on top of visualizations. Only applies to those interactions that don't show "data loading" animation. A value equal to or less than zero will disable the stale data overlay.	

Default Value	150	
Required	No	
Object/Name	preloadDetailsPopup	
Description	Data to be shown in the <i>Details</i> pop-up is preloaded as part of the visualization data request. If set to false , then the details data will be loaded on demand.	
Default Value	true	
Required	No	
Object/Name	forceClientSelectionHandling	
Description	If set to true , then selection handling in the visualizations will be performed by the client. If set to false , then the server will calculate the selection.	
Default Value	false	
Required	No	
Object/Name	subscriptionCompression	
Description	Controls if data query strings longer than 2048 chars should be compressed by the web client before sending them to the server.	
Default Value	false	
Required	No	
Object/Name	pdfMultiplePagesEnabled	
Description	Controls the visibility of the "Create multiple pages" checkbox in the ad hoc PDF report dialog.	
Default Value	true	
Required	No	
Object/Name	startUrl	
Description	URL used by the Home and Back buttons, and by the dialog for unexpected errors.	
Default Value		
Required	No	
Object/Name	useBrowserHistoryToNavigateBack	
Description	If set to true, the Back button will execute window.history.back() when pressed. This setting takes precedence over having a configured startUrl.	
Default Value	false	
Required	No	
Object/Name	hideThemeSelection	
Description	Controls the visibility of the theme drop down.	
Default Value	false	
Required	No	
Object/Name	Object/Name dataLoading.transport	

Description	Controls which transport should be used when loading data from the server and receiving notifications. Valid values are "websocket" and "long-polling". If configured to "websocket", but the WebSocket connection fails, then the web client will automatically fall back on "long-polling".	
Default Value	"websocket"	
Required	No	
Object/Name	dataLoading.connectTimeout	
Description	Controls the timeout used, in milliseconds, when opening the data loading connection to the server.	
Default Value	10000	
Required	No	
Object/Name	preventVisualizationMouseWheelDefaultEvents	
Description	Prevents the browser default action when using the mouse wheel over a visualization. Useful in an embed scenario if the hosting web page is scrolled when the user tries to zoom in a visualization using the mouse wheel.	
Default Value	false	
Required	No	
Object/Name	webGlEnabled	
Description	Enables the use of WebGL in visualizations that supports it.	
Default Value	true	
Required	No	
Object/Name	maxClipboardLength	
Description	Maximum length of text that will be attempted to be put into the system clipboard (copy). If too much text is attempted, then the browser might become unresponsive.	
Default Value	500000	
Required	No	
Object/Name	selectionInDetailsPopup	
Description	Enables/disables selection data in the visualization details popup. Primary use case for this setting is to disable it on a server level.	
Default Value	true	
Required	No	
Object/Name	showAlertsButton	
Description	Controls the visibility of the Alerts workbook button.	
Default Value	true	
Required	No	
Object/Name	showBackButton	
Description	Controls the visibility of the Back workbook button.	

Default Value	true	
Required	No	
Object/Name	showBookmarksButton	
Description	Controls the visibility of the Bookmarks workbook button.	
Default Value	true	
Required	No	
Object/Name	showCopyDashboardImageButton	
Description	Controls the visibility of the Copy Image workbook button.	
Default Value	true	
Required	No	
Object/Name	showHomeButton	
Description	Controls the visibility of the Home workbook button.	
Default Value	true	
Required	No	
Object/Name	showPdfExportButton	
Description	Controls the visibility of the Create PDF Report workbook button.	
Default Value	true	
Required	No	
Object/Name	showRefreshDataButton	
Description	Controls the visibility of the Refresh workbook button.	
Default Value	true	
Required	No	
Object/Name	showPauseRealtimeButton	
Description	Controls the visibility of the Pause Real-Time workbook button.	
Default Value	true	
Required	No	
Object/Name	showExcelExportButton	
Description	Controls the visibility of the Create Excel Report workbook button.	
Default Value	true	
Required	No	
Object/Name	pluginDenyList	
Description	Array of plugin IDs, used to block the specified dashboard parts and visualizations.	
Default Value	empty array	

Required	No	
Object/Name	pluginAllowList	
Description	Array of plugin IDs, used to allow only the specified dashboard parts and visualizations. The default value, an empty array, allows all plugins.	
Default Value	empty array	
Required	No	
Object/Name	showFileUploadUI	
Description	Controls the visibility of UI that is used to upload a file to the server.	
Default Value	true	
Required	No	
Object/Name	showLinkToFileUI	
Description	Controls the visibility of UI that is used to specify a data file on the server local file system as a data source. Per default, this flag is automatically inserted into the client configuration at runtime.	
Default Value	true	
Required	No	
Object/Name	partCreator.showLegacyButton	
Description	Controls the visibility of the Show Legacy switch button in the Select part panel. Used to show/hide legacy visualization parts.	
Default Value	true	
Required	No	
Object/Name	partCreator.legacyVisible	
Description	Default value of Show Legacy switch button in select part panel.	
Default Value	false	
Required	No	
Object/Name	maxrowcount	
Description	Controls the maximum number of rows a table can return.	
Default Value	100000	
Required	No	
Object/Name	preventDataLoadOnMaxRowCountExceeded	
Description	Controls whether an exception is raised when number of rows from the data table exceeds maxRowCount or should the rows be truncated.	
Default Value	true	
Required	No	
Object/Name	connectors.showLegacyButton	

Description	Controls the visibility of the Show Legacy Connectors switch button in the select	
	connector panel. Used to show/hide legacy connectors.	
Default Value	true	
Required	No	
Object/Name	connectors.legacyVisible	
Description	Default value of Show Legacy Connectors switch button in select connector panel.	
Default Value	false	
Required	No	
Object/Name	autoBucketingEnabled	
Description	Controls if automatic time bucketing columns should be created.	

NOTE

- With the new application configuration files, the workbook/config.js inside the extracted war file is no longer valid.
- If there are no config files available on the server, default ones will be created and saved. After that, you can alter them in any way you would like and keep the configuration even if the server is restarted.

MAP TILE PROVIDER CUSTOMIZATION

When creating a Map Plot visualization, the map images are retrieved from a map tile provider on web URL. Panopticon provides a default map tile provider preconfigured within the software. In addition, custom map tile providers can be added to the server configuration by editing the following file:

/etc/panopticon/appdata/default-settings/tileproviders.json

The default map tile provider that is shipped with the product can be overridden by specifying a different one and use the providerId **Default**.

In case the tileproviders.json file is deleted or moved and hence not found on server startup, then a new default tileproviders.json file will be created in the default-settings folder.

NOTE

You will not be able to keep the original default map tile provider with a different name. The original default will become unavailable for as long as the new map tile provider service with the name **Default** exists in the configuration.

Each provider is a name-value pair object with the following parameters:

Parameter	Description	
providerId	The name label that will be visible in the selection dropdown in the settings of the Map Plot visualization. This value must be unique across all map tile providers saved in the file.	
minZoom	The default value is 0 . This is the minimum zoom level that should be available in the Panopticon Map Plot when using this map tile provider. However, the minimum zoom level available from the tile service may be a higher value (e.g., 5). Refer to the documentation of the map tile service provider.	
maxZoom	The default value is 18 . This is the maximum zoom level that should be available in the Panopticon Map Plot when using this map tile provider. However, the maximum zoom level available from the tile service may be a higher value (e.g., 20) or a lower value (e.g., 15). Refer to the documentation of the map tile service provider.	
tileSize	The default value is 256 . This is the size of each tile image coming from the map tile service. It describes a raster size, 256 by 256 . Some services also use 512 by 512 . NOTE: It is required to have the correct tileSize setting for the service you are using. Otherwise, the tiles received will not be positioned correctly in the Map Plot and you will not see a correct map. Refer to the documentation of the map tile service provider. If the tile size is not specified by the map tile provider, assume 256 .	
urlFormat This is the URL of the map tile provider, and it will be different for each map provider. For map tile providers that use the OSM tile coordinates encoding, the URL with $\{z\}/\{x\}/\{y\}$.png or $\{z\}/\{x\}/\{y\}$.jpg, which for Panoptibe changed into $\{0\}/\{1\}/\{2\}$.png or $\{0\}/\{1\}/\{2\}$.jpg. Some providers will require an API key, which is appended as a URL request para on this form: ?apikey=abc123. For map tile providers that use the QUAD_KEY tile coordinates encoding, the will contain a {quadkey} reference which for Panopticon must be changed {0}.		
tileCoordEncoding	The default value is OSM . This value means that the map tile service uses the same URL principle as OpenStreetMap, where each tile URL request contains $/\texttt{zoomlevel/x-coord/y-coord/}, \text{ which corresponds to } / \{0\}/\{1\}/\{2\}/\text{ in the urlFormat.}$ Value QUAD_KEY means that the map tile service uses the QuadKey principle, for example, like what Bing maps do. QuadKey is short for Quadtree Key, which is a one-dimensional string of digits, created from the two-dimensional X-Y coordinates. A Quadkey uniquely identifies a map tile at a specific zoomlevel.	

Additional Information About the URL Format

In the URL of map tile providers using the OSM tile coordinates encoding, **{0}** represents the zoom level value **z**, **{1}** represents the x-coordinate value **x**, and **{2}** represents the y-coordinate value **y**. For any actual map tile URL, these will have been replaced by coordinate numbers (integers) by Panopticon before the request for a tile is sent to the map tile provider server.

The Map Plot in Panopticon takes care of inserting those numeric values as required, instead of the **{0}** and **{1}** and **{2}** values. When you read the service documentation from map tile service providers, you will notice that instead of referencing **{0}**, **{1}**, **{2}**, they will be referencing **{z}**, **{x}**, **{y}**.

NOTE

- You must replace z,x,y with 0,1,2 when using the URL in Panopticon.
 Also, some services will present a URL which includes a dollar sign, like /\${z}/\${x}/\${y}. These dollar signs must be removed.
- Raster Tiles are supported.
- Vector tiles are not supported.

Notes on using Google Maps or Bing Maps

In Panopticon, the configuration of a custom map tile provider is static. The configuration is saved in a JSON file which is read by Panopticon on start up, and any change of the information will require a server restart. For this reason, it is not practical to use either one of Google Maps map tile servers or Bing Maps map tile servers, because:

- ☐ The Google Maps API requires that an API key is first used to retrieve a session token, with a POST request. Map tiles are subsequently loaded with GET requests from a URL where both the API key and the session token must be appended as URL request parameters. This means that the map tile URL will no longer work when the session token expires.
- The Bing Maps API has frequently changing map tile URLs, and to get currently valid map tile URLs, you must start by making a request to a special API endpoint, which returns currently valid map tile URLs as well as various metadata about the map tiles. This means that the map tile URL will work for some time, but eventually will become invalid.

Implications of Moving a Workbook to Another Server

If a workbook using a custom map tile provider is exported from one Panopticon server and imported into another Panopticon server which does not have a custom map tile provider by that providerId name, then the Map Plot will display as blank--only marks/dots will show, but no map images. This can be corrected by changing the configuration of the Map Plot to use the **Default** map tile provider, or any other custom map tile provider added to that server.

Consequences of File Editing Mistakes

If the file tileproviders.json is not properly configured, for example if a quote character or comma or curly bracket is missing anywhere, then only the Panopticon default map tile provider will be available.

The server log will display any of the following warnings:

Unexpected end-of-input: expected close marker for Object
Illegal unquoted character
Cannot construct instance of `com.panopticon.server.core.web.repository.file.SettingFileRepository\$TileProviders`
Unexpected character ('{' (code 123)): was expecting double-quote to start field name

These are some examples of map tile providers:

https://wiki.openstreetmap.org/wiki/Raster_tile_providers

https://stadiamaps.com/

https://www.maptiler.com/

https://www.thunderforest.com/

https://www.maptilesapi.com/

Here's a useful website for comparing different tile maps side by side:

https://mc.bbbike.org/mc/

LICENSING

Licensing within Panopticon Real Time supports the following license types:

- A volume-based XML file (named **PanopticonLicense.xml**) that is used to store all license information for a specific customer, must be copied to the designated AppData folder (i.e., **/etc/panopticon/appdata**)
- Altair Units license which is available in Altair's License server you are connected to (local or over the network)
- Managed Altair Units license via Altair One

The license file type you will use is delivered separately from the installation packages.

NOTE

In the Panopticon documentation, HyperWorks Units (HWU) and Hosted HyperWorks Units (HHWU) are now named Altair Units.

In the Panopticon product, these license types are still named HyperWorks Units and Hosted HyperWorks Units.

For more information on Altair Units, visit https://www.altair.com/altair-units/.

Using Altair Units License in Altair's License Server

If your license source is Altair's License server, it is required to configure the following properties in the Panopticon.properties file located in the AppData folder or /etc/panopticon/appdata:

Property	Licensing
Attribute	license.hwu.uri
Description	The path where the License Server is running e.g., 6200@191.255.255.0 where the syntax is PORTNUMBER@HOST. If multiple servers are specified, use the ';' semicolon separator sign for Windows and the ':' colon separator sign for Linux. NOTES: If value is not set in the Panopticon.properties, the environment variable ALTAIR_LICENSE_PATH serves as the backup path and will be used.

Example	For Windows: license.hwu.uri=6200@192.168.5.51;6200@192.168.5.52 For Linux: license.hwu.uri=6200@192.168.5.51:6200@192.168.5.52
Default Value	
Property	Licensing
Attribute	license.mode
Description	The license mode. Possible values are FILE or HWU. Must be set to HWU .
Default Value	FILE

For example:

license.hwu.uri=6200@192.168.5.51;6200@192.168.5.52 license.mode=HWU

NOTE

 Panopticon Real Time supports different user roles which check out different numbers of Altair Units.

Role	Altair Units License Draw
Viewer	2
Designer	2 10 when designing a workbook
Administrator	2

- Alerts and scheduled tasks are leveled towards each other. Regardless
 of the number of alerts or scheduled tasks a user creates, only two
 Altair Units licenses will be checked out.
- These units are separate from the units that are checked out for a user of the server. For example, if a user is logged on to the server (two units) and starts an alert (two units), a total of four units are checked out. If the user starts two more alerts and a scheduled task, the total number of checked out units will still be four. If the user logs out without shutting off any alerts, two units will remain checked out.
- Two products (e.g., Panopticon Real Time and Panopticon Streams) or two instances of one product, must not be configured to use Altair unit licensing if they run on the same Tomcat.

Using Managed Altair Units License Via Altair One

Using the Altair Units licensing will support simplifying the license management by removing all manual aspects of emailing license files, extending evaluation periods, among others.

In addition, Altair Units licensing will help small to medium deployment customers who do not want to host on-premise license server.

Before using Altair Units, it is required to configure the following properties in the Panopticon.properties file located in the AppData folder or Petc/panopticon/appdata:

Property	Licensing	
Attribute	license.hwu.hosted	
Description	Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing.	
Default Value	false	
Property	Licensing	
Attribute	license.hwu.hosted.authorization.username	
Description	Username to the Altair One account.	
Default Value		
Property	Licensing	
Attribute	license.hwu.hosted.authorization.password	
Description	Password to the Altair One account.	
Default Value		
Property	Licensing	
Attribute	license.hwu.hosted.authorization.token	
Description	An authorization token generated through the Altair One admin portal. Used to authorize a machine to the managed Altair Units system.	
Default Value		

NOTE

• To use the managed Altair Units licensing, set the following properties:

license.hwu.hosted=true
license.mode=HWU


- Add the Panopticon application to your Altair One account.
- When using Managed Altair Units via Altair One, you do not need to configure the license.hwu.uri attribute. This is because, the URL or host where the Managed Altair Units servers are running is already set internally in the Altair License JDK and any value entered by the product user will be ignored.

To authorize the machine against the managed Altair Units system, you have two options.

Option 1


Use an authorization code generated through Altair One:

Log on to Altair One (https://admin.altairone.com) then navigate to User Profile and select Authorized Machines.



2. Click Generate Auth Code

The page displays the auth code and a timer indicating the code's expiration.



Click Copy to Clipboard to copy the generated auth code.

3. Paste the generated code into the license.hwu.hosted.authorization.token property in the Panopticon.properties file.

4. Start the server.

Option 2

Directly use your Altair One credentials in Panopticon.properties:

- 1. Enter your Altair One credentials into the license.hwu.hosted.authorization.username and license.hwu.hosted.authorization.password properties in the Panopticon.properties file.
- 2. Start the server.

NOTE

- If a token is entered, this will be tried first. If the token was invalid or not present, and
 credentials are present, the credentials will be used to authorize the machine towards the
 managed Altair Units system.
- In Option 1, the generated auth code is only valid for 15 minutes and you should restart your server within that timeframe to properly get access to your licenses.
- In Option 2, Altair One credentials are only required at first restart of the server to generate the auth token and should be removed from the Panopticon.properties file going forward to avoid exposing these credentials.
- A working Internet connection is required to use Altair Units licensing.
- If your company uses proxy, you might need to add exception in your proxy to allow access to the Managed Altair Licenses.

Please refer to this link for more information:

https://community.altair.com/kb_view.do?sys_kb_id=bb9bf3fc97205590e3b0361e6253af03

Or see Managed Altair Units License SSL Error section below.

• If you don't have an Altair One account, you can sign up for a free trial that will allow you to test the product for 14 days.

Proxy Server Configuration

When using Managed Licensing, where the Altair License Manager server is hosted by Altair in the cloud, it is possible to let Panopticon go via a proxy server when communicating with the ALM. For example, this can be useful when the Panopticon server needs to be isolated from general internet connections.

Scenario 1: Transparent proxy. This does not require any special configuration.

Scenario 2: Traditional proxy. Using Altair License Utility (ALMutil) and filling in details on the Managed Licensing tab, the proxy server details are written to a configuration file in the home directory of the user, from where the Altair Licensing SDK (ALSDK) that is embedded in Panopticon, will read them. This is part of the Panopticon license checkout, and the proxy server details are used for communication with the license manager. This means that Altair License Utility must be run under the user that also runs Tomcat and Panopticon.

Using CLI ALMutil, there is also the option of setting up a system-wide configuration file of the same kind.

Using a command with the following format:

```
almutil -proxy -system -host <host> -port <port> [-user <user ID> -passwd <password>]
```

You will produce the following configuration files which on a Linux system by default are saved under /usr/local/altair:

- altair hostedhwu.cfg
- ☐ altair hostedhwu ex.cfg

NOTE

If the proxy requires no credentials, the second file is empty. These .CFG files are created in /usr/local/altair unless the environment variable ALM_HHWU_CONFIG is defined. If you would like these files to be created in a different directory, define the variable ALM_HHWU_CONFIG before running almutil. For example:

export ALM_HHWU_CONFIG=/apps/altair/license

To test the connectivity with the Altair One cloud license servers, run the following command:

```
almutil -conntest
```

Next, authorize the Panopticon host machine by running the command below. Here ${\tt NNNN}$ should be replaced with the Auth Code generated from the Altair One account.

```
almutil -alauth -system -anyhost -code NNNNN
```

Finally, configure Panopticon in Panopticon.properties with the following values:

```
license.hwu.hosted.authorization.password=
license.hwu.hosted.authorization.token=<auth code>
license.hwu.hosted.authorization.username=
license.hwu.hosted=true
license.hwu.uri=<proxyport>@<proxyhost>
license.hwu.use_client_timezone=true
license.mode=HWU
```

Managing File Handles

In some cases, the Tomcat process that runs the Panopticon server may run out of file descriptors, which are handles used by the operating system to access a file (file handles). Panopticon data connections and license units checkouts count towards the total number of file handles in use.

When the maximum limit of file handles (open files) is reached, you cannot open any additional files, or make any additional TCP connections, or check out additional Altair license units.

On a Linux system, maximum file handles limit (open files) and other limits such as memory usage are called Resource Limits or rlimits. The rlimit values can be viewed and changed using the ulimit command and various arguments to that command. Please refer to Linux documentation for details on using the ulimit command, for example https://linux.init.com/linux_ulimit_command/.

The system will have an overall limit (global system maximum) as set in the kernel variable file /proc/sys/fs/file-max. In addition, there are rlimits set for each process, or for each user running a process. The rlimits for any given process will have a soft limit and a hard limit. The soft limit is what will be in effect, and the hard limit says what the maximum is if you want to raise the soft limit.

The reason for setting rlimits specific for a process that are lower than the overall system rlimits, is that you want to economize system resources between several processes to ensure that no single process consumes all available system resources, thereby causing problems for other processes. Likewise, a process specific rlimit set lower than the system maximum is also useful for protecting the system, avoiding system total resource depletion.

Identifying the Problem

When a user encounters the maximum limit of file handles in Panopticon, data connection or logging into Panopticon could fail. To confirm that Panopticon has hit the file handle limit, you should look for this message in the Panopticon log:

(Err: 60) Out of file descriptors suitable for socket operation

In conjunction with the error message above, you may also see the following messages in the Panopticon log:

com.panopticon.server.core.exception.HyperWorksUnitsLicenseException: Unable to check out a license java.lang.Throwable: Altair License Manager: License error

Other things that could indicate that Panopticon has reached the maximum limit for file handles, but can also have other reasons, are:

otn	ther reasons, are:	
	The browser console may show error messages like:	
	Unable to check out a license	
	The dashboard may show the following message when you click the Edit button:	
	Unable to edit – HWU license error	
	The dashboard may show the following when a Viewer wants to open a workbook:	
	AW Snap ! Unable to checkout license; Go to workbook overview	

Enabling Event Poll to Avoid False Warnings

Altair Units License checkouts count towards the total number of open files. The Altair Units License SDK by default uses the **select(2)** interface in Linux to monitor the number of available file handles or sockets. The highest number that select(2) can return is **1024**. This means that as soon as 1024 or more file handles are open, the license server process will not see any available file descriptors.

However, the Altair Units License SDK can also use the **epoll(7)** interface in Linux, which is not suffering from the limitation of select(2). To make the ALSDK use epoll(7) instead of select(2), you must set an environment variable as follows:

LMX_USE_EPOLL=1

Still, epoll(7) is nonetheless bound by the rlimit settings, which means that in addition to setting the above environment variable, you may also need to raise the open files rlimit for the Tomcat process, by using the ulimit command.

CONFIGURATION PROPERTIES

Encoding

The default encoding of the JVM is the same as the system it is running on. It is recommended to configure your Java and Apache Tomcat to use the UTF-encoding. This is achieved by setting the property file.encoding to UTF-8.

There are several ways to configure the property and one method is to create a seteny file in your Apache Tomcat bin folder:

<pre>setenv.bat</pre>	101	VVIIIUOWS
-----------------------	-----	-----------

■ setenv.sh for Linux

The following operating systems should contain the following information in order to use the UTF-8 encoding:

For Windows:

```
set JAVA OPTS=%JAVA OPTS% -Dfile.encoding=UTF-8
```

For Linux:

```
JAVA OPTS="$JAVA OPTS -Dfile.encoding=UTF-8"
```

Restart the Apache Tomcat to save the changes.

PROXY

A proxy is a server or software running on a server that acts as an intermediary for requests from clients seeking resources from other servers. Instead of using a proxy, you can use a <u>load balancer</u>.

It is recommended to use a proxy when setting up Panopticon Real Time. There are a variety of proxies available. One of the most commonly used proxies is Apache HTTP Server with the proxy module. Refer to the section below on how to setup an Apache HTTP Server with Proxy functionality.

Apache HTTP Server

This section describes the steps on how to install and configure an Apache Proxy. The guide expects that the Apache HTTP Server is being set up for the first time. Please note that the installation steps might vary depending on your environment. These steps cover how to install and configure an Apache HTTP Server with proxy support for Microsoft Windows.

- Download the Apache HTTP Server from the official webpage: https://httpd.apache.org/download.cgi
- 2. Unzip and copy the files to a folder.
- 3. Configure the proxy by opening the httpd.conf file in the conf folder.
- 4. Update the SRVROOT variable. The value must be updated to the file location of the Apache HTTP server.

```
Define SRVROOT "/Path/To/Apache"
ServerRoot "${SRVROOT}"
```

5. Modules are required to be loaded to make the Apache HTTP Server into a proxy. Add the following lines in the httpd.conf file.

```
LoadModule proxy_module modules/mod_proxy.so
LoadModule proxy_http_module modules/mod_proxy_http.so
LoadModule proxy_wstunnel_module modules/mod_proxy_wstunnel.so
LoadModule rewrite module modules/mod rewrite.so
```

NOTE

In the httpd.conf file:

- Ensure that the line Include conf/extra/httpd-vhosts.conf is uncommented.
- Replace Listen 80 with Listen 10088.
- 6. Configure the logic for the proxy and how requests should be passed. The Virtual host config should look like this and be added to the httpd-vhosts.conf file in the conf/extra folder:

```
<VirtualHost :10088>
   ServerAdmin webmaster@localhost
   ProxyPreserveHost On
   ProxyPass /panopticon http://localhost:8080/panopticon
   ProxyPassReverse /panopticon http://localhost:8080/panopticon
   ProxyPass /panopticon/server/ws http://localhost:8080/panopticon/server/ws
   ServerName localhost:8080
   RewriteEngine on
   RewriteCond %{HTTP:UPGRADE} ^websocket$ [NC]
   RewriteCond %{HTTP:CONNECTION} Upgrade [NC]
   RewriteRule . ws://localhost:8080%{REQUEST_URI} [P]
</VirtualHost>
```

7. The Apache HTTP Server can be started when all the configurations are in place. This is done by running the httpd script or application in the Apache bin folder.

LOAD BALANCER

A load balancer is a server used to distribute the workload across multiple computer resources. A load balancer allows you to scale the system to max and optimize the resource use and throughput, and at the same time minimize the response time. A load balancer can also be used to ensure that the system will still be available, even during downtime on a computer resource.

Very much like proxies, there are a variety of load balancers available. The only requirement Panopticon Real Time has on the load balancer is that it supports persistence or stickiness. This means that the proxy will establish a user session and ensure that the user continues to use the same computer resource.

For performance reasons, mostly related to in-memory caching of results from user-specific queries, ensure that a specific user is always directed to the same Panopticon server instance, at least for the duration of the session.

When the user starts a new session, they can typically be directed to any server instance in the cluster. To make the authentication token cookie mechanism to work when this happens, you should also set up <u>token synchronization</u> between servers.

For details on how to configure multiple servers to run in a cluster and synchronize content between them, see <u>Server Cluster Configuration</u>.

Apache HTTP Server

The following section describes the steps on how to install and configure an Apache Load Balancer. The guide expects that the Apache HTTP Server is being set up for the first time. Please note that the installation steps might vary depending on your environment. These steps cover how to install and configure an Apache HTTP Server with proxy support for Microsoft Windows.

- Download the Apache HTTP Server from the official webpage: https://httpd.apache.org/download.cgi
- 2. Unzip and copy the files to a folder.
- 3. Configure the proxy by opening the httpd.conf file in the conf folder.
- 4. Update the SRVROOT variable. The value must be updated to the file location of the Apache HTTP server.

```
Define SRVROOT "/Path/To/Apache"
ServerRoot "${SRVROOT}"
```

5. Modules are required to be loaded to make the Apache HTTP Server into a load balancer. Add or uncomment the following lines in the httpd.conf file.

```
LoadModule proxy_module modules/mod_proxy.so
LoadModule proxy_http_module modules/mod_proxy_http.so
LoadModule proxy_wstunnel_module modules/mod_proxy_wstunnel.so
LoadModule rewrite_module modules/mod_rewrite.so
LoadModule headers_module modules/mod_headers.so
LoadModule lbmethod_byrequests_module
modules/mod_lbmethod_byrequests.so
LoadModule proxy_balancer_module modules/mod_proxy_balancer.so
LoadModule slotmem_shm_module modules/mod_slotmem_shm.so
```

6. Configure the logic for the load balancer and how requests should be passed.

In the following example, we have configured the load balancer to listen to port **10080** and to use two balancer members (**Route 1** and **Route 2**). The example will also set a session cookie named **ROUTEID**. The cookie contains the route that the user took and will continue to use throughout the active session.

```
<VirtualHost *:10080>
   ServerAdmin webmaster@localhost
   ProxyPreserveHost On

Header add Set-Cookie "ROUTEID=.%{BALANCER_WORKER_ROUTE}e; path=/"
env=BALANCER_ROUTE_CHANGED

<Proxy "balancer://panopticoncluster">
   BalancerMember "http://localhost:8080/panopticon" route=1
   BalancerMember "http://localhost:8081/panopticon" route=2
   ProxySet stickysession=ROUTEID
   </Proxy>

ProxyPass /panopticon balancer://panopticoncluster
   ProxyPassReverse /panopticon balancer://panopticoncluster
   ServerName localhost:8080
</VirtualHost>
```

7. The Apache HTTP Server can be started when all the configurations are in place. This is done by running the httpd script or application in the Apache bin folder.

MULTIPLE INSTANCES

Multiple instances of Panopticon Real Time can be deployed onto a single machine.

The common usage models for multiple instances are:

- ☐ Multi-tenant deployments, providing separate **Sand boxes** for each tenant
- ☐ Multi environments (Development, Test, Production)
- Regression Testing
- ☐ To deploy multiple servers, the WAR and corresponding configuration file must be updated to have a unique name.

BACKUP

Panopticon stores all its data in two locations:

- The <AppData> directory, including the content repository which is in the <AppData>/.repository/subdirectory (usually hidden by default by the OS).
- ☐ The cluster shared store, which by default is in the subdirectory <appData>/shared/but can be reconfigured to an external location, see section Synchronizing Tokens.

To back up and restore the complete state of the server:

- 1. Back up (or restore) the entire <AppData> directory.
- 2. If you've changed cluster.store.type to something other than **DIRECTORY**, then you should back up (and restore) that location too. Scripts that export or import the cluster content to/from a directory on disk can be provided by Altair on request.
- 3. You may opt to back up the server log files from <tomcat-home>/logs/too.

DATA ACCESS AND CACHING


Panopticon assumes in general that data is never at rest and too big to be simply loaded into memory. The data can either be subscribed against or polled (automatically refreshed on a defined period).

This means either:

- Load Subset of Data in Memory
- Load Summary and Parameterized Detail Views
- ROLAP (Dynamically explore datasets)

Consequently, for direct access, Panopticon is only as fast as the underlying data platform, or the refreshing of result set caches.

When data is not changing on a timely basis, such as a daily updated data warehouse, there is the additional option of retrieving data into a data store.



Consequently:

- Only required data is retrieved. Majority of the data stays in the underlying data sources.
- □ Typically aggregated, conflated, filtered data is retrieved.
- ☐ Behind each dashboard part (visualization) is a micro-cube.
- Each cube is designed for streaming real time updates.
- ☐ Behind each cube is a real-time data table (also powering filters).
- ☐ Behind each data table is a resultset cache.
- □ Behind the cache is the underlying data repository.
- Caches can be loaded on the fly, or pre-loaded on a periodic basis.
- □ All caching is optional.
- □ Consequently, data access is either:
 - Work Directly against underlying sources (either Exploratory Analysis (ROLAP), Or Pre-Defined Parameterised Views)
 - Import data into the Data Store

Usage is typically **Hybrid**. Based on the characteristics of the underlying data, you choose whether to import to Data Store, or query directly.

This is to cater for real world data landscapes, where different data has different data retrieval latency characteristics, and different timeliness; and where there is too much data to simply load it all into memory.

CONTENT REPOSITORY

Previous versions of the server stored workbook files in the Workbooks subdirectory of the application data directory (i.e., /etc/panopticon/appdata/Workbooks), and older versions of those workbooks in the Archive subdirectory (i.e., /etc/panopticon/appdata/Archive). Starting with the 2020.0 release, workbooks are now stored in a version tracking repository, located in the .repository subdirectory (i.e., /etc/panopticon/appdata/.repository).

The repository also stores other types of content that was previously stored in separate subdirectories of the application data directory, such as data files and bookmarks.

The new workbook repository tracks changes to content, folders, and permissions. It also makes it possible for multiple servers to synchronize their repositories, so you only have to make changes to a workbook on one node in a server cluster, and it will automatically propagate to the other servers [see section on cluster configuration].

The first time you start the 2020.0 server, it will initialize an empty repository in the application data directory. If you are upgrading an existing install, you have the option of migrating content from the old application data directory into the new repository [see section on content migration].

For the list of properties that control the repository behavior, refer to those starting with 'repository.' in the Properties: Panopticon section.

SERVER CLUSTER CONFIGURATION

When you have multiple servers running, you can set them up, so they synchronize content between them. The servers will use an internal protocol over http(s) to propagate changes and make sure their content is the same.

The cluster component discovers the other servers and the topology that connects them and can use various methods to do so. The cluster component also identifies one of the running servers as the **leader**, the others are **followers**.

The leader-follower relationship determines how content is synchronized. A follower will immediately push any local change to the leader, for example, when you save a workbook after editing it. On the other hand, a follower periodically polls the leader for changes. This means the leader has the "latest" version of the content, whereas a follower may lag by a few seconds. The leader is also special if there are conflicting changes, for example, if two users edit and save the same dashboard. In this case, the leader's changes always win.

The REST services, that the servers call to synchronize content, expose potentially sensitive information such as data tables and data source settings. They are protected by token validation just as other services on the server, and only accept special "server" tokens that are never issued to users. A server can only get a token from another server if they have both been configured with the same shared secret. That said, the calls are not encrypted, so if you connect two servers over the internet, you will want to use HTTPS.

Even though the content synchronization makes it easier to run a set of servers as a cluster behind a load balancer, you still need to use sticky sessions (session affinity). The server requires that a single user stays with the same server instance for the duration of a session.

There are four different cluster modes:

None - Each server is completely stand-alone, and nothing will be synchronized. This is the default, and no further configuration is needed.
Fixed - One server is the permanent leader. The other servers will synchronize with it if it is up. If the leader goes down, the followers will log the problem, but will continue to run basically as stand-alone servers. When the leader comes back up, they will start synchronizing again.

In practice, the fixed mode has a single point of failure. Because the followers connect through the leader, even if they keep running, their content will not be synchronized, and conflicts become more likely the more their content diverge.

To configure fixed mode, set cluster.shared.secret to the same non-empty string on all, set cluster.mode to FIXED on all, and then set cluster.fixed.leader to the URL of the leader on the followers only (leave it blank on the leader).

The leader URL should be the path to the web application, for example

http://panoserver:8080/panopticon/. It needs to identify the leader server and be resolvable on the network that the followers run on. If you use a load balancer, you cannot use the externally exposed URL, as it always needs to resolve to the leader server. If the leader server is dynamically assigned an IP, you need to take extra steps to assign it with a URL that does not change.

Bully - The server with the lowest ID (lexicographically) of the running servers is chosen as leader, and if it goes down a new leader is automatically appointed.

When a new server joins a bully cluster, it needs to discover the current list of members and their IDs. To do this, it tries to contact any running server from a list of known servers, called the boot servers. If any one of them answers, it replies with the current members and leader. If none of them answers, it starts as the single member of the cluster if it is one of the boot servers, or refuses to start if not.

In a sense, the bully mode is more flexible than the fixed mode since it eliminates the single point of failure. As long as one server is still running, there will be a leader, so synchronization will happen. In another sense, it's less flexible as you need to provide more non-changing URLs, one for each server.

To configure the bully mode, set cluster.shared.secret (see above), set cluster.mode to BULLY on all, set cluster.bully.id to a unique ID string for each server (lower ID has higher leader priority), set cluster.bully.bind on each to the URL on which the other servers can reach it, and cluster.bully.boot to a comma-separated list of known server URLs.

An example bully configuration with three servers:

On server #1:

```
cluster.shared.secret=supersecretpassword
cluster.mode=BULLY
cluster.bully.id=panopticon-1
cluster.bully.bind=http://192.168.0.10/panopticon
cluster.bully.boot=\
http://192.168.0.10/panopticon,\
http://192.168.0.11/panopticon
```

On server #2:

```
cluster.shared.secret=supersecretpassword
cluster.mode=BULLY
cluster.bully.id=panopticon-2
cluster.bully.bind=http://192.168.0.11/panopticon
cluster.bully.boot=\
http://192.168.0.10/panopticon,\
http://192.168.0.11/panopticon
```

On server #3:

```
cluster.shared.secret=supersecretpassword
cluster.mode=BULLY
cluster.bully.id=panopticon-3
cluster.bully.bind=http://192.168.0.12/panopticon
cluster.bully.boot=\
http://192.168.0.10/panopticon,\
http://192.168.0.11/panopticon
```

Note that only servers #1 and #2 are boot servers, and that only id and bind differ between servers. With this configuration, servers #1 and #2 can be started in any order, but at least one of them must be up before #3 starts. On the other hand, you can add server #3 without #1 and #2 knowing about it up front, so non-boot servers can be useful in auto-scaling scenarios.

One caveat with non-boot servers is that if all the boot servers go down, a non-boot server will become the leader. If a new server joins, or a boot server rejoins, there is no way for them to see this, and you will end up with two separate clusters.

Kubernetes - The servers discover each other through the Kubernetes API Server, and the one whose pod has the lowest name (lexicographically) is chosen as leader. Each server periodically refreshes this information, so if the list of available pods changes, they adapt.

To call the Kubernetes API, the server needs to know the address of the API Server and have valid credentials. By default, the address is passed into the pod via Kubernetes downward API as environment variables KUBERNETES_SERVICE_HOST/PORT, and the credentials are mounted to /var/run/secrets/kubernetes.io/serviceaccount/, and the server will use these, so no extra configuration is needed.

The server discovers the other servers (pods) with a Kubernetes label selector. You can use any label and any selector for this, e.g., give each pod the metadata label "app" with value "panopticon" and use the selector "app=panopticon". The server will assume that all pods returned by the guery are standard Panopticon servers.

You also need to tell each server what its own pod name is, so it can tell if it's supposed to be a leader or follower and avoid calling itself. You can use the Kubernetes downward API to pass this in: use valueFrom, fieldRef and fieldPath "metadata.name" (see example below).

To configure the Kubernetes mode, set cluster.shared.secret (see above), set cluster.mode to KUBERNETES, set cluster.kubernetes.id to the pod's name, set cluster.kubernetes.label_selector to the pod selector, and cluster.kubernetes.peer path to the web application path.

If the pod that runs the Panopticon server container also runs other containers, the first container will be used. If this is not the case, you can set cluster.kubernetes.container_name to the name of the container that runs the Panopticon server.

Example yaml snippet:

```
template:
 metadata:
    labels:
     app: panopticon
  spec:
    containers:
      . . .
      enw.
        - name: CLUSTER SHARED SECRET
          value: supersecretpassword
        - name: CLUSTER MODE
          value: KUBERNETES
        - name: CLUSTER KUBERNETES ID
          valueFrom:
            fieldRef:
              fieldPath metadata.name
        - name: CLUSTER KUBERNETES LABEL SELECTOR
          value: app=panopticon
        - name: CLUSTER KUBERNETES PEER PATH
          value: panopticon/
```

SYNCHRONIZING TOKENS

When a user has authenticated successfully with a server, a token is issued that is passed back and forth in a cookie. These tokens may be long-lived with a default expiration time of seven days and normally automatically reissued. So, when the server is regularly used, the user will rarely need to log in again. Similarly, API tokens never expire.

Normally, a token issued by one server is only valid on that server. The server keeps track of issued tokens and validates each incoming token against its stored tokens. Furthermore, tokens are revoked when an administrator logs out a user, and the token is removed from the server's list.

If there are multiple servers that are being used as a cluster with a load balancer in front, they should be configured to have synchronized tokens. Even if the load balancer uses sticky sessions as it should, a token is typically valid for a longer time than a session lasts, and the user should not have to log in again just because a new session is directed to a different server than last time.

Token synchronization uses a different mechanism from repository synchronization. The repository stores content with its change history, and there are scenarios where the user may want to synchronize one and not the other. For example, there may be one QA server, and one production server then use a common login.

Tokens are synchronized through the cluster shared store. By default, this is just a subdirectory <AppData>/shared/ which is not synchronized. The server also uses this store for other types of data that should be shared between servers but isn't technically content (i.e., fonts that have been uploaded, scheduled tasks, most recently viewed workbooks of users, and other things).

To enable cluster store synchronization:

Change the property cluster.store.type from its default DIRECTORY to some other supported type (see following section).
Configure the selected store type (again, see below).
Ensure all servers use the same cookie name in authentication.token.cookie, or a cookie issued by one server would not be visible to another.
Ensure all servers (i.e., validating server and the one that issued the token) have the same <appdata>/token_secret. This secret is used to sign and validate tokens.</appdata>

Cluster Shared Store: ZooKeeper

You can use <u>Apache ZooKeeper</u> as the shared storage for a Panopticon <u>server cluster</u>. After installing ZooKeeper run it as a separate external server, and then instruct Panopticon how to connect to it. Simply put, ZooKeeper is a hierarchical key-value store. ZooKeeper can also run in replicated mode with failover if you want to ensure that the cluster shared store does not become a single point of failure.

To choose ZooKeeper as cluster store:

- 1. Install ZooKeeper and ensure it is running when Panopticon starts.
- 2. Change the cluster.store.type property from its default value DIRECTORY to ZOOKEEPER.
- Add the (required) property cluster.store.zookeeper.connect and set it to a standard ZooKeeper connect string. This is a comma-separated list of one or more ZooKeeper servers in <host>:<port>[/<chroot>] format.

Example:

```
cluster.store.type=ZOOKEEPER
cluster.store.zookeeper.connect=zkhost1:2181/pano,zkhost2:2181/pano
```

NOTE

We recommend that you use the optional chroot path as in the example above to only give Panopticon access to a subtree of the ZooKeeper data.

EXPORTING LEGACY FILES

Starting with Panopticon 2020.0, the new server installation will no longer include Workbooks and Data folders in the AppData folder. To recreate these folders and export workbooks and their associated data files, GroupAccessRestrictions, and parameters that are stored inside the repository, you can either:

do a POST call to http://[host]:[port]/[serverappname]/server/rest/server/export/legacy/files?replaceExistingDataFiles=true&replace ExistingWorkbooks=true

Example:

http://localhost:8080/panopticon/server/rest/server/export/legacy/files?replaceExistingDataFiles=true&replaceExistingWorkbooks=true

- or perform the following steps
- 1. Set the documentation.enabled property in Panopticon.properties to true.

documentation.enabled=true

- 2. Restart the server.
- 3. Access the REST API to call the /rest/server/export/legacy/files service using this URL:

http://[host]:[port]/[serverappname]/swagger-ui.html

Example: http://localhost:8080/panopticon/swagger-ui.html

The Panopticon REST API page displays.

- Select legacy in the Select a Definition drop-down list.
- 5. Expand the Server section and find the Export Legacy Files service then run it.

If successful, the Data and Workbooks folders are recreated in the AppData folder with the exported workbooks, data files, parameters, and GroupAccessRestrictions.

UPGRADING PANOPTICON REAL TIME

The server stores all its content in the AppData (e.g., /etc/panopticon/appdata) directory. Ensure that you back up this directory frequently. You can always revert the server to an earlier state by restoring the entire AppData directory from a backup.

In general, a newer server will use an AppData from an older server, with exceptions for some types of content that you may need to migrate manually. In contrast, the server will refuse to start if you point an older server to an AppData that has been used with a newer server.

NOTE

Two servers should never share the same AppData directory.

It is recommended that you try out the new server version with your existing content before you decide to upgrade. The best way to do this is on a dedicated server machine, or at a minimum on a separate Tomcat instance. You should use a separate AppData directory for the new server while you are evaluating it --- if for some reason you decide to wait with the upgrade, you will not be able to use the new version's AppData on the old server, even if you have not made any changes.

Summary of steps:

- 1. Make a full backup of the old server's AppData directory.
- 2. Configure a new Tomcat, ideally on a separate machine.
- 3. Put the new server WAR file in the new Tomcat's webapps directory.
- 4. Copy the entire AppData from the old server to the new server.
- 5. Make sure the new server is pointed at the new AppData copy.
- 6. Read below for how content is migrated between versions.
- 7. Start the new server and then review its log file carefully to see if there were any warnings related to migration.
- 8. Try out the new server. Keep in mind that content created or changed on the new server cannot be moved back to the old server if you decide to roll back.
- 9. If you have continued to use the old server in parallel with testing, you should copy over the AppData again to make sure you have the latest content.

Content Migration

The format of the AppData changes between versions. Certain types of content may be moved to a different location with the AppData e.g., bookmarks from loose files into the repository for version tracking and cluster replication. Frequently, new features may be added to the content which may include changes to the content models, e.g., workbooks with new property. Typically, a newer server version will do this migration behind the scenes when it first starts up, and any issues found will be logged with at least a warning level.

NOTE

After starting a new server version for the first time, check the log file for warnings. It is much easier to address these issues immediately than later on, for example, if you wish to redo a one-time migration step.

By default, the server will check for content in an old location in AppData and do a one-time migration of anything it finds when it starts. Typically, the server will copy old content from loose files into the repository. This type of migration is controlled through the repository.migrate.<type>.path properties in Panopticon.properties.

For example, in versions 21.1 and older, the server stored workbook bookmarks as loose files in the AppData/Bookmarks/ directory. Version 21.2 stores them inside the repository in AppData /.repository/instead. The property repository.migrate.bookmarks.path defaults to Bookmarks which is relative to AppData and therefore points to the 21.1 bookmark files. When the 21.2 server starts, this can happen:

There are no bookmarks in the repository but are available in $AppData/Bookmarks/$ or to some other location you have set the property to. The server will do a one-time migration and move them into the repository. The result of this will be logged. The old bookmark files are left in the old location but will no longer be used.
There are bookmarks in the repository. You may have created them on the new server, or the migration has run already. In this case, it does not matter if the old location has bookmarks or not, and the server will log a warning that it will not run a second migration. To get rid of the warning, simply blank out the property value.
There are no bookmarks in either location, but the property is still set. This would be the default on a new server. In this case, you will get a false migration warning because the server cannot find

AppData/Bookmarks/. Again, just blank out the property value to get rid of the warning.

NOTE

- Because the server will not migrate a type of content (e.g., bookmarks) if that
 type of content is already in the repository, you will need to delete the
 repository to run the migration again. The easiest way is to start over with the
 AppData from the old server.
- After the content has been migrated, the original files are left in the old location in AppData. They are no longer used, to clean up, you may want to delete them after you have checked the logs for any migration issues.

There are some types of content that have changed so much between releases that they cannot be automatically migrated like this.

Workbooks and their history in version 17 and older were stored separately in AppData/Workbooks/ and AppData/Archive/. You can use the repository.migrate.workbooks.path and repository.migrate.archive.path properties to migrate them, but we do not default these to the old locations (e.g., you may not want to migrate the entire history), and for clarity you need to use absolute paths if you set them.

Data files used with text data sources can now optionally be stored in the repository so they can be bundled with the workbook, and replicated to other servers in a cluster. You can still have data files in AppData/Data/, so old workbooks will continue to work on new servers, but old files are not automatically migrated into the repository.

Permissions on workbook folders were in version 17 and older stored in XML files in the AppData/Workbooks/subtree. The permissions model has changed completely since then, so they are not automatically migrated. To migrate permissions from version 17, you need to:

- 1. Use PCLI <u>convertpermissions</u> to create a permissions template which, as closely as possible, reflects the old permissions. This is a single JSON file which the new server can apply to its repository.
- 2. Review the generated permissions template in a text editor to make sure it is correct.
- 3. Point the repository.startup.apply.permissions.path to the template file and start the server. You can control how the template is applied with the properties repository.startup.apply.permissions.clean and repository.startup.apply.permissions.create.
- Clear the properties after the server has started, or they will be applied on each startup overwriting changes you
 make.

Authentication tokens are server specific. They will only work on a new server if it has the same /token_secret">AppData>/token_secret contents as the old server that created them. In addition, a normal user token is also stored as cookie in the user's browser and will only get sent to a new server if it has the same URL as the old server. For these reasons, tokens are not automatically migrated, and users will have to log in again.

The exception to token migration is API tokens. In version 21.1 and older, these were stored in AppData/APIToken/. In 21.2, all tokens, including the API tokens, are stored in the shared cluster storage (even if

you only have one single server), by default in AppData/shared/tokens/. See also the section on Synchronizing Tokens. If the server finds API tokens in the old location, they will be migrated on startup.

[3] AUTHENTICATION

Panopticon Real Time provides multiple approaches to authentication. It can easily be configured to use different authentication methods depending on the environment and the setup. Panopticon does not have any support for user management or administration of users.

Authentication in Panopticon is a two-step process:

- 1. The user provides their identity using the selected method.
 - The username, which should be unique across all users, and their list of user groups are provided. The user groups can have arbitrary names and have no special meaning in Panopticon, but you can use them to set permissions on folders.
- 2. Assign roles to the users, effectively deciding what they can do.

All authentication-related settings should be made in the <appdata>/security.yml file. The server creates a template for this file when it starts if it's not already there. For more information on the YAML format, see the Appendix.

ASSIGN ROLES

Users can have one or more roles in Panopticon:

Role	Description
Viewers	Allowed to look at workbooks.
Designers	Allowed to create and edit workbooks.
Administrators	Allowed to have access to features like logs, API tokens, and scheduled tasks.

Map your users to Panopticon roles using their user group memberships and usernames. Groups are preferred to avoid listing individual users in the configuration.

The following properties control the mapping and take a comma-separated list of one or more values. Each property is optional.

Property	Description
access.administrator.groups	List of group names where all members become administrators.
access.administrator.users	List of individual usernames of users that become administrators.
access.designer.groups	Groups where members become designers.
access.designer.users	Usernames of users that become designers.
access.viewer.groups	Groups where members become viewers.
access.viewer.users	Usernames of users that become viewers.

There are two more properties that control role mapping:

Property	Description
access.default.roles	Applies to users that are not listed in the regular mapping, either explicitly with username, or as members of a listed group. The possible values are VIEWER (default), DESIGNER , and ADMINISTRATOR.
access.list.delimiter	Can be used to change the default comma as separator in the access mappings to something else if your usernames or group names contain commas.

Example role mapping settings:

access: administrator.groups: pano-admins, managers administrator.user: cto@company.org designer.groups: pano-editors, pano-reviewers viewer.groups: pano-users default.roles: VIEWER

In an organization where only selected users should have access to Panopticon, you have two options:

☐ The authentication approach (preferred)

Configure the authentication layer so that only authorized users are let in. For example, with LDAP, use an OU in your user-dn-patterns that only has Panopticon users as members, or with OAuth, assign only these users to the application.

☐ The content access control approach (fallback)

Change the permission of the Panopticon content root folder so that the group names associated with the viewer and designer roles have access and remove the permissions for **Everyone**.

NOTE

Users that are administrators always have full access to all folders.

GENERAL SETTINGS

You can allow anonymous users to use Panopticon. In this mode, a user can browse workbooks and view them

without first logging in. The UI will display a normal permissions.



button that users can click to authenticate and get their

Permission settings can be done in the following properties:

Property	Description
authentication.required	Set to false to allow anonymous use. The default value is true .
authentication.logout.success-url	When a user logs out of Panopticon by clicking the Logout button at the bottom of the right-hand profile pane, they are normally redirected back to the <i>Welcome</i> page. If you have authentication required, this will trigger authentication again, and if you use single sign-on your user may be automatically logged in again.

Add and set to send users somewhere else.

NOTE: This can also be useful if you are hosting Panopticon inside a larger application.

METHODS

You can use any of the methods below to authenticate users, but you can only have one method selected at a time. The server will not start if you have enabled more than one. Example configuration for each is given in the default security.yml file. Select a specific method by adding or uncommenting the related properties in the configuration.

Panopticon uses **Spring Security** for authentication. Properties below that start with spring. all have their default names and can be looked up in the Spring documentation. Properties that start with authentication. are Panopticon-specific.

Some properties below have sensitive information such as passwords. If you do not want to store them in clear text in security.yml you can move them to Secret.properties.

Username and Password

This is the default method and will be used if you have no other method-related properties in security.yml. In this mode, the server expects a list of users and their groups in the <appdata>/users.xml file. The server creates a template for this file when it starts if it's not there already.

NOTE

- The default users.xml has example users, but they are all commented out.
 This means that out of the box, the server will use username and password, but has no known users, so you can't really log in until you provide more configuration (i.e., there will be a single viewer user named user with a one-time random password).
- Use this mode for testing and very simple setups only.

LDAP

To use the Lightweight Directory Access Protocol (LDAP) as authentication method, first configure the connection to your LDAP server and a user that has permissions to search users and groups. For example:

```
spring.ldap:
   urls: 'ldap://ldap-host-name:389/'
   username: 'cn=admin,dc=company,dc=org'
   password: 'admin123'
   base: 'dc=company,dc=org'
```

The spring.ldap.base property is optional and can be used to define a root which the rest of the configuration is relative to.

Next, define where to find the users. Panopticon uses bind authentication against LDAP, so it will try to log in to the LDAP server with the credentials entered by the user. In the example below, **{0}** is a placeholder where the entered username will be substituted.

```
authentication.ldap:
   user-search.base: ou=sales
   user-search.filter: (objectClass=user)
   user-dn-patterns: uid={0},ou=users
```

NOTE

user-search is optional but useful if you have a complicated user structure. You can list multiple user-dn-patterns if you separate them with semicolon.

Finally, tell Panopticon how to find each user's group memberships. Here, **{0}** is a placeholder where the user's full DN will be substituted.

```
authentication.ldap:
   group-search.base: ou=groups
   group-search.filter: (member={0})
   group-role-attribute: cn
```

Active Directory

To use Active Directory (AD) as an authentication method, you need to first configure the AD server. Then provide the following:

```
authentication.active-directory:
   urls: ldap://host-name:389/
   domain: company.com
```

Field	Description
urls	This field is mandatory and can take multiple URLs, if necessary, but they must be separated.
	The port can be 389 or 3268 . With the latter, Panopticon does a global search in AD which is useful if there are multi/subdomain set up. However, the Panopticon server cannot extract groups from it because memberOf properties would be missing.
domain	This field is optional. If it is not defined, you can provide the login name as someone@somecompany.com. Otherwise, simply log on as someone assuming the domain is set to somecompany.com.

OAuth 2.0

A typical OAuth configuration looks like this:

```
spring.security.oauth2.client:
    registration:
    our-okta-app:
        client-id: 0odfhiuhvb5d7
        client-secret: r7rFsdgkjsdgpUXB
        scope: openid, profile, groups
provider:
    our-okta-app:
    issuer-uri: https://dev-8052349.okta.com
```

our-okta-app is a name that you choose yourself for the registration. Tthis is because Spring Security normally supports multiple registrations. It can be anything, but it needs to be the same in both locations, and it affects the redirect URI.

From the OAuth server, you need three things: the ID and secret for the client that you have registered there for Panopticon, and the URI to the server itself. The scope should be enough to retrieve the user's username and user groups, and the application should be configured to return the groups in a claim.

On the OAuth server side, you need to register a Panopticon endpoint as a valid **sign-on redirect URI** (or similar). This endpoint is /login/oauth2/code/<reg-name>, where <reg-name> is what you chose for the registration in security.yml. For example,

https://company.org/analytics/login/oauth2/code/our-okta-app, assuming you expose Panopticon at https://company.org/analytics.

Panopticon gets the username from the preferred_username claim, and the user groups from the groups claim by default. If you want to use other claims, this can be configured via:

```
authentication.oauth2.username-claim (default preferred_username)authentication.oauth2.groups-claim (default groups)
```

The configuration above only works if the OAuth server exposes the default metadata endpoint (i.e., /.well-known/openid-configuration or /.well-known/oauth-authorization-server). If it does, Spring Security can get most of the necessary configuration from there. If not, you need to manually provide this configuration. The list of available properties can be found here and other resources on the web:

https://docs.spring.io/spring-security/reference/6.1/servlet/oauth2/login/core.html#oauth2login-boot-property-mappings

SAML 2.0

A typical SAML configuration looks like:

```
spring.security:
    saml2.relyingparty.registration:
    our-okta-app:
        assertingparty:
        metadata-uri: https://login.company.org/sso/saml/metadata
```

our-okta-app is a name that you choose yourself for the registration. This is because Spring Security normally supports multiple registrations.

On the SAML server side, you need to register a Panopticon endpoint as the **single sign-on URL** (or similar). This endpoint is /login/saml2/sso/<reg-name>, where <reg-name> is what you chose for the registration in security.yml. For example, https://company.org/analytics/login/saml2/sso/our-okta-app, assuming you expose Panopticon at https://company.org/analytics.

Panopticon uses the NameID element in the SAML response as the user's username and gets the user groups from the groups attribute. If you want to use an attribute as username, or a different attribute for the groups, this can be configured via:

authentication.saml2.username-attribute (Default not set, use NamelD)
authentication.saml2.groups-attribute (Default groups)

You get the metadata-uri from the SAML server. Spring Security will fetch the rest of the required configuration from there. If this doesn't exist, or is not publicly exposed, you need to manually provide the rest of the configuration. The list of available properties can be found here and other resources on the web:

https://docs.spring.io/spring-security/reference/6.1/servlet/saml2/login/overview.html#servlet-saml2login-minimalconfiguration

https://github.com/spring-projects/spring-boot/blob/3.1.x/spring-boot-project/spring-boot-autoconfigure/src/main/java/org/springframework/boot/autoconfigure/security/saml2/Saml2RelyingPartyProperties.java

NOTE

When Panopticon initiates a SAML login, it stores verification information in the user's HTTP session. To find and validate this after the login, it is critical that the browser passes the session cookie back. By default, SAML finishes with a cross-site POST which the browser considers insecure and therefore omits the cookie. To make an exception for the session cookie, add this to security.yml:

```
server.servlet.session:
   cookie.same-site: None
   cookie.secure: true
```

This sets SameSite=None on the cookie, instructing the browser to include it in the cross-site POST. Cookies can only have this attribute if they also have Secure set. This means that you must use HTTPS with these settings.

If the SAML server requires that you sign the SAML requests, you need to provide a pair of credentials: a **private key** and the corresponding **public certificate**. The certificate used to validate the signatures on SAML responses is automatically downloaded with the metadata.

AUTHENTICATION COOKIE

To reduce the number of times that a user is required to log in, you can configure a JWT cookie that will be sent to the user's browser. This cookie is backed by a corresponding file in <appdata>/shared/tokens/ and can only be used to authenticate if the cookie is still valid and the token file exists.

The properties that control the cookie all have the prefix authentication.token. and should be set in security.yml:

Property	Description
cookie.name	The cookie name. The default value is ptoken .
cookie.domain	The cookie domain. The default is not set.
cookie.path	The cookie path. The default is not set. Consequently, the context path from the incoming request is used.
cookie.http-only	Determines whether the cookie should be accessible to JavaScript. The default value is false .
cookie.secure	Determines whether the cookie should be only sent over HTTPS. The default value is not set. Assign the flag if the incoming request is secure.

cookie.max-age	Determines for how long the cookie is valid. The default value is 7d (seven days). If you do not specify a unit, the value is in number of seconds.
cookie.same-site	Determines if the cookie can be passed across sites. The default value is Lax , and the other options are Strict and None .
refreshable	Determines whether the cookie should be renewed automatically if the user is active. The default value is true .

The JWT token cookies are signed and validated using the contents of the <appdata>/token_secret file. The server creates this file with random contents if it doesn't exist when it starts. However, in scenarios where you want cookies to be valid across multiple servers (e.g., when running them in a cluster), you need to make sure that they all have the same file contents.

SECURITY HEADERS

Spring Security enables many HTTP security headers by default. This is according to recommendations and best practices.

However, there may be scenarios where you want to customize or disable some of them (for example, to run the Panopticon JavaScript API examples).

The headers frame-options policy property controls the X-Frame-Options header. Valid values are **DENY** (default), **SAMEORIGIN**, or **blank** (to disable).

MIGRATE

Panopticon started to use Spring Security in 2024.1, and with this came changes to the security-related configuration. One major difference is that we decided to move the security settings to the new <appdata>/security.yml file.

This was done for two reasons. First, the Panopticon.properties file cannot have comments, and explicitly lists every available property, even the ones with default values and the ones that are not used. Second, many Spring properties have very long and repeated prefixes, and the YAML format makes this much easier to read.

The properties that have moved all start with authentication. or access. and your original ones in Panopticon.properties will be left there after upgrading, but you will get a warning message in the server log each time it starts until you have moved them out of there. Also note that authentication method-related properties have changed radically.

You now select authentication method by configuring it. For example, if you previously had OLAP and SAML properties set up, and switched between them with authentication.type, you can now have both configured in security.yml and switch by commenting one of them out.

Spring Security now provides web application protection, so it takes over some aspects that were previously handled by Tomcat. For example, some security headers and the CORS filter are now configured in security.yml too.

Miscellaneous

The authentication.token.secret value has moved out into the <appdata>/token_secret file. It should get migrated automatically, but you may want to double-check that the file contents are the same as the old value. This makes sure that JWT token cookies issued by the old server are still valid but is also important if you manually configured this value (e.g., to run servers in a cluster).

The authentication.logout.redirect.url property is now named authentication.logout.success-url and is set in security.yml.

Username and Password

If you used <tomcat-home>/conf/tomcat-users.xml to list your users, you need to move them from there into <appdata>/users.xml. Note that the syntax is different, and because the Spring Security format expects hashed passwords by default, you need to prefix them with {noop} if you want to store them in clear text.

NOTE

 $\verb|authentication.type=BASIC| is no longer needed. Username and password are the default method.\\$

LDAP

Previously, you would configure LDAP through a JNDI realm in the Panopticon web application's context file, e.g. <tomcat-home>/conf/Catalina/localhost/panopticon.xml, or possibly globally in web.xml.
You now do it in security.yml instead, and the property names are different from the XML attributes you used:

Realm Attribute Name	Property Name
connectionURL	spring.ldap.urls
connectionName	spring.ldap.username
connectionPassword	spring.ldap.password
userPattern	authentication.ldap.user-dn-patterns
userBase	authentication.ldap.user-search.base
userSearch	authentication.ldap.user-search.filter
roleBase	authentication.ldap.group-search.base
roleSearch	authentication.ldap.group-search.filter
roleName	authentication.ldap.group-role-attribute

NOTE

You no longer need ${\tt authentication.type=BASIC}$. This meant username and password authentication (of which LDAP is a special case) and this is now the default.

OAuth 2.0

If you had OAuth configured in Panopticon.properties, you would only need a few values from there. Move them into security.yml as follows:

authentication.oauth2.client.id goes to client-id in the registration.
 authentication.oauth2.client.secret becomes client-secret.
 authentication.oauth2.login.scope becomes scope but comma-separated.
 authentication.oauth2.login.url becomes issuer-uri but remove the endpoint path.
 authentication.oauth2.identity.attribute.username becomes authentication.oauth2.username-claim but only if it's not preferred_username.
 authentication.oauth2.identity.attribute.roles becomes

authentication.oauth2.groups-claim but only if it's not groups.

IMPORTANT

The endpoint in Panopticon that the OAuth server should redirect to after authentication has changed in, what you used to have in login.callback.url, from /server/rest/auth/login, to the Spring Security standard path/login/oauth2/code/<reg-name>. You need to update the sign-in redirect URI or similar on the OAuth server side to reflect this.

Also note that Panopticon now has support for OpenID Connect (OIDC), which it previously didn't, so if you had to tweak the configuration before to avoid OIDC, you no longer must do that.

For example, if your Panopticon.properties had this:

```
authentication.oauth2.client.id=0odfhiuhvb5d7
authentication.oauth2.client.secret=r7rFsdgkjsdgpUXB
authentication.oauth2.identity.attribute.roles.pattern=
authentication.oauth2.identity.attribute.roles=pano-groups
authentication.oauth2.identity.attribute.username=preferred username
authentication.oauth2.identity.method=HEADER
authentication.oauth2.identity.url=https\://dev-
8052349.okta.com/oauth2/v1/userinfo
authentication.oauth2.login.callback.url=http\://company.org/panopticon/serve
r/rest/auth/login
authentication.oauth2.login.redirect.url=
authentication.oauth2.login.response.type=code
authentication.oauth2.login.scope=openid profile groups
authentication.oauth2.login.url=https\://dev-
8052349.okta.com/oauth2/v1/authorize
authentication.oauth2.logout.redirect.url=
authentication.oauth2.logout.url=https\://dev-
8052349.okta.com/oauth2/v1/logout
authentication.oauth2.token.method=BODY
authentication.oauth2.token.url=https\://dev-8052349.okta.com/oauth2/v1/token
authentication.type=OAUTH2
```

Then your security.yml should look like this:

```
spring.security.oauth2.client:
    registration:
    our-okta-app:
        client-id: 0odfhiuhvb5d7
        client-secret: r7rFsdgkjsdgpUXB
        scope: openid, profile, groups
provider:
    our-okta-app:
        issuer-uri: https://dev-8052349.okta.com
authentication.oauth2.groups-claim: pano-groups
```

And you should change the sign-in redirect URI (or similar) on your OAuth server from

http://company.org/panopticon/server/rest/auth/login to http://company.org/panopticon/login/oauth2/code/our-okta-app.

SAML 2.0

If you had SAML configured in Panopticon.properties, you would only need a few values from there. Move them into security.yml as follows.

- authentication.saml.identityprovider.url can be used to guess the metadata-uri (try appending /metadata to it), but it's safer to look it up on the SAML server side.
- authentication.saml.assertion.username becomes authentication.saml2.username-attribute, but if the NameID in your SAML responses already has the username you can just leave it out.
- authentication.saml.assertion.roles becomes authentication.saml2.groups-attribute but only if it's not groups.

IMPORTANT

The endpoint in Panopticon that the SAML server should redirect to after authentication has changed in what you used to have in assertionconsumerservice.url from /server/rest/auth/login () to the Spring Security standard path /login/saml2/sso/<reg-name>. You need to update the single signon URL or similar on the SAML server side to reflect this.

For example, if your Panopticon.properties had this:

```
authentication.saml.assertion.roles=pano-groups
authentication.saml.assertion.username=uname
authentication.saml.assertionconsumerservice.url=http\://company.org/panoptic
on/server/rest/auth/login
authentication.saml.certificate.name=1
authentication.saml.certificate.password=wasspord
authentication.saml.challenge.required=true
authentication.saml.identityprovider.certificate.file=/pano-creds/okta.cert
authentication.saml.identityprovider.logout.url=
authentication.saml.identityprovider.signature.validation.required=true
authentication.saml.identityprovider.url=https\://dev-
8052349.okta.com/app/panosaml/exki7b0XIFO5d7/sso/saml
authentication.saml.keystore.file=/pano-creds/key.p12
authentication.saml.keystore.password=wassport
```

```
authentication.saml.keystore.type=PKCS12
authentication.saml.login.redirect.url=
authentication.saml.logout.redirect.url=
authentication.saml.openam.meta.alias=
authentication.saml.protocolbinding=
authentication.saml.provider=OPENSAML
authentication.saml.serviceprovider.id=http\://www.okta.com/exki7b0XIFO5d7
authentication.type=SAML
```

Assuming NameID already had the same value as the uname attribute, then your security.yml should look like this:

```
spring.security:
    saml2.relyingparty.registration:
    our-okta-app:
        assertingparty:
        metadata-uri: https://dev-
8052349.okta.com/app/panosaml/exki7b0XIF05d7/sso/saml/metadata
        signing.credentials:
        - private-key-location: file:/pano-creds/key.pem
        certificate-location: file:/pano-creds/cert.pem

authentication.saml2.groups-attribute: pano-groups
```

And you should change the single sign-on URL (or similar) on your SAML server from http://company.org/panopticon/server/rest/auth/login to http://company.org/panopticon/login/saml2/sso/our-okta-app.

NOTE

Spring Security wants the signing credentials as two separate files: the **private key** and the **public certificate**. You may need to export them from your keystore.

[4] ADDITIONAL OR OPTIONAL STEPS

FILE UPLOAD SIZE LIMITS SETTINGS IN TOMCAT AND PANOPTICON

Starting with version 2020.0 and the introduction of web authoring, any connection to a file data source involves uploading the file first to the server then loading its data into Panopticon. The upload happens as part of using the data connector for the file.

Setting the limit of the file upload sizes are done in the following properties:

□ maxSwallowSize

This setting is part of the overall Tomcat configuration, particularly for the HTTP connector, and is found in the <tomcat>/conf/server.xml file.

maxSwallowSize controls how much data Tomcat will accept for upload before it is cancelled or terminated. If the file size is larger than the file.upload.size.max.bytes, and the limit of maxSwallowSize is hit, then Panopticon will never get a chance to send a proper error message about the file being too large. The upload will simply be terminated with a message about an unknown error. It is therefore recommended to set the maxSwallowSize value high enough to the file size that Panopticon users are expected to load.

Any minus value (e.g., -1), means unlimited. Setting a minus value for maxSwallowSize creates a risk of getting the Tomcat connection saturated by a very large file upload or being stuck in an infinite file upload. A reasonable setting would be something between one to two times of the Panopticon file.upload.size.max.bytes property value.

Example:

file.upload.size.max.bytes

This property is part of the Panopticon specific settings found in the <u>Panopticon.properties</u> file in the PanopticonAppdata folder (i.e., /etc/panopticon/appdata).

This size limit property (in bytes) controls how large the files Panopticon will accept to connect to for loading data.

If the file exceeds the size limit, there will be an informative error message that indicates the current size limit. The size limit check can only take place on the condition that the file has already been successfully uploaded to the server. The upload success depends on the limit set in maxSwallowSize.

TOMCAT MEMORY CONFIGURATION FOR LINUX

NOTE

It is recommended to increase the Java heap size of Tomcat to avoid the initiation of garbage collection when memory usage hits the set threshold.

The steps may vary depending on how Tomcat was deployed.

Steps:

- 1. Stop Tomcat.
- 2. Create a file named setenv.sh.
- 3. Place the file in the Tomcat bin folder.
- 4. Set the minimum and maximum heap size with the JVM -Xms and -Xmx parameters. A minimum of 1 GB is recommended. For example:

JAVA_OPTS="\$JAVA_OPTS -Dfile.encoding=UTF-8 -server -Xms512m -Xmx2g"

NOTE

Setting the maximum value should be dependent on your system. Ensure that the heap size is not larger than the available free RAM on your system. It is recommended to use 80% of the available RAM not taken by the operating system or other processes of your JVM.

- 5. Save the file.
- 6. Restart Tomcat to apply the increase in the heap.

TOMCAT MEMORY CONFIGURATION FOR WINDOWS

NOTE

It is recommended to increase the Java heap size of Tomcat to avoid the initiation of garbage collection when memory usage hits the set threshold.

Steps:

- 1. Stop Tomcat.
- 2. Create a file named setenv.bat.
- 3. Place the file in the Tomcat bin folder.
- 4. Set the minimum and maximum heap size with the JVM -Xms and -Xmx parameters. A minimum of 1 GB is recommended. For example:

set JAVA OPTS=%JAVA OPTS% -Dfile.encoding=UTF-8 -server -Xms512m -Xmx2g

NOTE


Setting the maximum value should be dependent on your system. Ensure that the heap size is not larger than the available free RAM on your system. It is recommended to use 80% of the available RAM not taken by the operating system or other processes of your JVM.

- 5. Save the file.
- 6. Restart Tomcat to apply the increase in the heap.

SET CLIENT AUTOMATIC RECONNECTION TO THE SERVER WHEN DISCONNECTED

When the client loses connection to the server, by default, it will no longer attempt to automatically reconnect to the server.

A notification message displays such as below. Clicking the Reconnect link will attempt to reconnect to the server.



The AppData folder of Panopticon Real Time has a subfolder named JavaScriptConfiguration which contains the file named workbook.json.

Below is an example default content of a \JavaScriptConfiguration\workbook.json file:

```
"baseUrl" : "..",
  "forceClientSelectionHandling" : true,
  "startUrl" : "../",
  "subscriptionCompression" : true,
  "dataLoading" : {
     "transport" : "websocket"
  },
  "webGlEnabled" : true,
  "pdfMultiplePagesEnabled" : true
}
```


To set automatic reconnection to the server, add the following parameter in the JavaScriptConfiguration\workbook.json file:

"automaticReconnectOnServerDisconnect" : true,

NOTE

After each change in the workbook.json file, the Panopticon application must be restarted.

A notification message is displayed below. Connection to server lost: attempting to reconnect...



AUTOMATIC LOGOUT OF USERS ON TIMEOUT TO SAVE UNUSED LICENSES

Users who have no activity and leave their browsers open may be logged out and their license units are checked out by setting the following properties in the Panopticon.properties file:

Property	Timeout Session			
Attribute	timeout.session.enabled			
Description	Boolean value stating if timeout functionality should be used or not.			
Default Value	false			
Property	Timeout Session			
Attribute	timeout.session.exception.delimiter			
Description	The delimiter to use for the usernames stated in the timeout.session.exception.usernames property.			
Default Value	, (comma)			
Property	Timeout Session			
Attribute	timeout.session.exception.usernames			
Description	Usernames that should be excluded from the timeout functionality. Separated by the delimiter stated in the timeout.session.exception.delimiter property.			
Default Value				
Property	Timeout Session			
Attribute	timeout.session.minutes			
Description	Minutes of inactivity before a user session is terminated by logging out the user.			
Default Value	480			
Property	Timeout Session			
Attribute	timeout.session.notification.minutes			
Description	Minutes before a timeout that a notification about session timeout is sent to the user.			
Default Value	1			

NOTE

- The timeout functionality is only enabled if property timeout.session.enabled is set to true.
- Each time a user actively interacts with the server, the timeout timer for that user is reset. Just sitting idle on a tab in the UI or having a dashboard open will not

reset the timer.

• If timeout.session.notification.minutes has been set to a value > 0, a notification will be sent to the user on an established notification subscription on the websocket, X minutes before the timeout happens. This is the format of the timeout notification:

```
{"TimeoutNotification":{"minutesUntilTimeout":1}}
```

 When a session times out, a logout notification will be sent on an established notification subscription on the WebSocket. This is the format of the logout notification:

```
{"LogoutNotification":{"reason":"Logged out due to session timeout"}}
```

 To abort a session timeout, all that is required is that the user interacts with the server. To facilitate the process there is a new service that can be called using GET on URL /rest/user/timeout/reset that will reset the timeout for the calling user. The service itself does not do anything, but the layers the message interacts with before reaching the service will count it as a user activity and resets the timeout.

SETTING THE TRANSPORTATION PROTOCOL

In previous versions, you can control which transportation protocol the browser would use for subscriptions to the server by setting the value (WEBSOCKET or LONG_POLLING) in the client.data.load.transport property in the Panopticon.properties file.

Starting with version 2020.2, you can instead edit the workbook.json and admin.json in <appdata>/JavaScriptConfiguration/, where you add the section:

```
"dataLoading" : {
    "transport" : "websocket" or "long-polling"
}
```

NOTE

After each change in the workbook.json and admin.json files, the Panopticon application must be restarted.

PANOPTICON REAL TIME CONFIGURATIONS FOR EMAIL SEND OUTS AND ALERTS

NOTE

When triggering <u>email send out via the REST API</u>, <u>scheduling</u> email send outs, or sending <u>email alerts</u>, Panopticon Real Time needs to be configured with valid email server information.

The following values need to be configured in the Panopticon.properties file located in the AppData folder (e.g., /etc/panopticon/appdata):

Attribute	Description			
email.address	Email address where the alert will be sent from.			
email.host	Host name used by the email server.			
email.password	Email password, if available. NOTE: When using a Gmail account, you must use an app password to authenticate with the Gmail SMTP server. See Sign in with app passwords for more information.			
email.port	Port number used by the email server.			
email.security.mode	Security mode used when sending emails. Possible values: NONE , SSL , TLS . The value NONE will be used if there was no value configured for the property.			
email.sender_name	Sender Name alias to use when sending email.			
email.username	Email account username.			

FONT INSTALLATION REQUIREMENT FOR PDFS AND IMAGE EXPORT WITH CJK CHARACTERS

When creating PDF reports or exporting images from workbooks that contain text in Chinese, Japanese or Korean (CJK), a font with CJK support is required. The font must be installed on the server operating system. Refer to your operating system documentation on how to install a new font.

The PDF and image export functionalities in Panopticon will use the font specified in the workbook <u>Theme</u>. While used in the browser, the workbooks and dashboards will get the suitable font by the browser if a font with CJK support is needed.

When creating a PDF or an image, the browser is not involved since it happens on the server-side, and correct characters depend on the availability of a font with CJK support on the local system of the server, plus the specification of that font (e.g., **Yu Gothic**), in the workbook Theme. For the list of CJK-supporting fonts, you may refer to https://en.wikipedia.org/wiki/List_of_CJK_fonts.

SETTING SERVER PROPERTIES THROUGH THE ENVIRONMENT VARIABLES

Server properties set in the <u>Panopticon.properties</u> file in the AppData folder (i.e., /etc/panopticon/appdata) are overridden by environment variables.

For example, you can supply a JSON object through the environment variable SPRING_APPLICATION_JSON that will be parsed during server start up:

NOTE

Ensure that you minify the JSON object before setting the environment variable.

This will override and set the following property values:

```
server.id=Test_Server
subscription.data.loading.pool.max.size=5
subscription.broadcasting.pool.max.size=6
```

As seen from the example above, you can use inline JSON annotations for properties that share the same prefix, which in this case is **subscription**.

To override a single property, create an environment variable with the same name, but replace each '.' with an '_' and use upper case.

Example: Override the property server.id
Name: SERVER_ID
Value: <some value>

You can also override individual properties with environment variables. Just set a variable with the same name as the property but with all letters in upper case and periods replaced with underscores. For example,

REPOSITORY_STARTUP_IMPORT_PATHS will override the repository.startup.import.paths in Panopticon.properties.

[5] ADVANCED SERVER DEPLOYMENTS

USAGE IN SSL ENABLED ENVIRONMENTS

Enabling SSL for Panopticon Real Time

The steps shown in this guide use the keytool and OpenSSL commands for managing keystores and certificates. The keytool command is part of the Java distribution and can be found in <code>JAVA_HOME\bin</code>. Make sure you have the <code>JAVA_HOME\bin</code> folder in your <code>PATH</code> environment variable to run the command.

■ Details on the keytool command can be found here:

https://docs.oracle.com/javase/8/docs/technotes/tools/unix/keytool.html

Details on the OpenSSL command can be found here:

https://www.openssl.org/docs/manmaster/man1/openssl.html

Follow the steps below to configure SSL for Panopticon Real Time using JKS/PKCS12 formats. For using the PEM formats directly inside Connector, please refer to the Apache Tomcat SSL document link at the end of this section.

Steps:

1. Change directory to the CATALINA_HOME\conf folder, which is where we want to generate the Tomcat keystore.

Do one from the following options:

Option 1. If you don't have a certificate and private key file

NOTE

Java is strict when validating the certificate of a host.

If the domain name store in the certificate does not match the domain of the server, the connection will be rejected. Enter the target domain name (www.mydomain.com) when keytool asks for "your first and last name", when running this command.

Create a keystore file to store the private key and self-signed certificate used to identify the server:

keytool -genkey -alias myalias -keyalg RSA -keystore keystore.jks

Option 2. If you already have a certificate and private key

NOTE

You may need to have Administrator rights to run this command.

```
openssl pkcs12 -export -name cast -in [certname].cer -inkey [certname].key -out keystore.jks
```

If the above OpenSSL command gives an "Unable to load certificate" error, the certificate may be in binary format. Then use the below two commands, to generate the JKS file.

```
openssl x509 -inform DER -in [certname].cer -out [certname].crt openssl pkcs12 -export -name cast -in [certname].crt -inkey [certname].key -out keystore.jks
```

2. Add an SSL HTTP/1.1 Connector entry in \$CATALINA_BASE/conf/server.xml

NOTE

The keystorepass should be the password you used while creating the keystore in Step 1.

- 3. Disable HTTP ports.
 - a. If you don't want to allow plain HTTP protocol, disable unencrypted server access by commenting out the default HTTP connector for port 8080.

b. If you want to redirect all HTTP traffic to HTTPS.

Then add a security constraint entry in \$CATALINA BASE/conf/web.xml.

NOTE

Make sure you assign the server.host.internal property when disabling the HTTP port. If not, PDF generation may stop working. For example:

server.host.internal=https://localhost:8443/panopticon

4. After completing the configuration changes, you must restart Tomcat. When the process is back up you should be able to connect over SSL using the URL below:

```
https://localhost:8443/panopticon
```

Details on how to configure Apache Tomcat SSL can be found at:

https://tomcat.apache.org/tomcat-9.0-doc/ssl-howto.html

Defining a TrustStore

In scenarios that require TLS-enabled intra-service communication, we need to configure a trustStore. These scenarios include, for instance, LDAP, SAML or OAuth integration.

A trustStore is essentially a keyStore, but where the keyStore is used to store private keys used to identify the server, the trustStore is used to store public keys of trusted *Certificate Authorities* (CA). The trustStore is used to verify certificates presented to the server when establishing an SSL connection.

Follow the steps below to create a new trustStore, import a certificate and configure Java to use the new trustStore:

Steps:

1. Create a new keyStore called **truststore**:

```
keytool -genkey -alias truststore -keyalg RSA -keystore truststore.jks
```

2. Export a certificate from a keyStore:

```
keytool -export -keystore keystore.jks -alias myalias -file [certname].cer
```

3. Import the certificate into the trustStore:

```
keytool -import -trustcacerts -alias myalias -file [certname].cer -keystore
truststore.jks
```

You can also re-use a keyStore as a trustStore in which case the certificate does not need to be exported and imported.

To configure a trustStore for Apache Tomcat you need to edit the JAVA_OPTS environment variable in the setenv script, located in the Tomcat conf folder.

☐ On Windows, setenv.bat:

set JAVA_OPTS=-Djavax.net.ssl.trustStore="C:/location/to/truststore
/truststore.jks"

■ On Linux, setenv.sh:

export JAVA_OPTS="\$JAVA_OPTS Djavax.net.ssl.trustStore='/location/to/truststore/truststore.jks'";

[6] AUTHORIZATION

SECURE ACCESS

Panopticon workbooks published to the folders or subfolders in Panopticon Real Time can be secured by granting allowed or denied permissions.

NOTE

Beginning with version 16.1.0, new workbooks must be published in a folder or subfolder to use their access restrictions.

However, workbook access restriction is still available and supported on older workbooks that will be accessed in the current and later Panopticon Real Time versions.

Creating Folders

A user with an Administrator role can create folders on the Workbooks and Data Library pages.

NOTE


Users that log on with a Designer role will have their personal folder created and displayed on the *Workbooks*, *Data Library*, *Webhooks*, and *Themes* pages (e.g., ~designer).

Personal folders:

- Are displayed and can be accessed for users with an Administrator or Designer role.
- Are where Designers can create workbooks and build dashboards. For more information, refer to <u>Altair Panopticon Web Authoring Guide</u> on how to create workbooks on the Web client.

Steps:

1. On the Workbooks or Data Library tab, right-click on the topmost folder, and select New Folder.



NOTE

Only Administrators are allowed to change the permissions on the root folder.


The Create Folder dialog displays.




NOTE

- **Everyone** is available in the *Allowed* section by default.
- Removing the Everyone group will mean that the folder and its subfolders will not be available for public access.
- The default group permissions on the root folder are WRITE + READ.
- 2. Enter the Folder Name.
- 3. Proceed to defining the Authorization to <u>Allowed</u> or <u>Denied</u> groups and users.
- 4. Click Create

The new folder is displayed on the expanded Folder hierarchy list and on the Root Folder list.






Adding Groups and Users with Allowed Authorization

A user with an Administrator or Designer role can grant permissions for users or groups to a workbook folder or subfolder.

Steps:

1. Right-click on a folder (except the root folder) and select **Permissions** in the context menu.



The Permissions dialog displays.



2. Under the Allowed section, click the \mathbf{Add}^{+} icon.

A new User/Group Allowed section is displayed.



3. Select **User** or **Group** to be given permission in the drop-down list.



- 4. Enter the user or group Name.
- 5. Select the permission level that will be granted to the user or group:
 - READ


Permission to read the folder.

READ + WRITE

Permission to write to the folder and read.


MODIFY + WRITE + READ

Permission to read, modify, and write to the folder as well as create subfolders.




7. You can either:


Select the Apply Permissions to Subfolders checkbox



This means the permissions that will be used on all of the subfolders will be fetched from the root folder.




- Leave the Apply Permissions to Subfolders box unchecked and modify the permission properties of the subfolders
- 8. Click Update to save the changes.



Adding Groups and Users with Denied Access

Steps:

1. Right-click on a folder and select **Permissions** on the context menu.



The Permissions dialog displays.



Under the *Denied* section, click the **Add** icon.
 A new *User/Group Denied* section is displayed.



- 3. Select **User** or **Group** that will be given denied permission in the drop-down list.
- 4. Enter the user or group Name.
- 5. Select the denied permission level that will be granted to the user or group:
 - MODIFY

Prevent user or group to modify and create subfolders.

WRITE + MODIFY

Prevent user or group to modify and write to the folder.

READ + WRITE + MODIFY

Prevent user or group to modify and create subfolders, modify and write to the folder, as well as read the folder.



6. Click . The user or group is added under the *Denied* list.




Repeat until all of the users with denied access are added.

7. Click to save the changes.


Creating Subfolders

Steps:

- 1. To create subfolders, you can either click a folder:
 - On the expanded Folder hierarchy list




On the Root workbooks/folders list




The Folders page is displayed.

2. Right-click on the folder and select **New Folder**.




Refer to <u>Creating Folders</u> for the steps in creating the subfolders. Also, <u>Adding Groups and Users with Allowed Authorization</u> and <u>Adding Groups and Users with Denied Access</u> for more information on adding Users and Groups with allowed or denied authorization.


The subfolder is added.



3. You can also opt to delete a subfolder by right-clicking on the folder and selecting **Remove** on the context menu as long as it does not contain published workbooks.



A confirmation message displays.






Updating Folder or Subfolder Properties

Steps:

- 1. To update folder properties, click a folder or a subfolder.
- 2. Right-click on the folder or subfolder and select **Permissions**.



The corresponding Permissions dialog displays.



- 3. Make the necessary changes such as new folder name, add or delete users and groups.
- 4. You can either:
 - Check the Apply Permissions to Subfolders box

This means the permissions that will be used on all of the subfolders will be fetched from the root folder.

 Leave the Apply Permissions to Subfolders box unchecked and modify the permission properties of the subfolders

NOTE


The **Apply Permissions to Subfolders** check box is not enabled when defining the permissions for a subfolder.

5. Click Update to save the changes.

Downloading a Workbook

A user with an Administrator or Designer role with READ + WRITE <u>permission</u> to the folder is allowed to download a copy of a workbook available in it.

Right-click on a workbook and select **Download** on the context menu.



A copy of the workbook is downloaded.


Exporting Workbook or Folder Bundle

NOTE

- Data files associated with workbooks will only be included in the download if they are available inside the repository.
- Users will only be able to download workbooks from folders where they have WRITE permission.

Steps:


1. Right-click on a workbook or folder and select **Export Bundle** on the context menu.



Workbook Folder or Subfolder Context Menu

Workbook Context Menu

A notification message displays.



- 2. Check the Include Data Files box to include the associated workbook data files in the download.
- 3. Click Download

 A copy of the workbook or folder bundle is downloaded.


Importing Workbooks Bundle

NOTE


- Users will only be able to import a bundle to folders where they have WRITE permission.
- Existing workbooks with the same name as the uploaded workbooks will be archived, only if the new workbook differs from the current one.
 Consequently, the uploaded version will be the current one.
- The bundle must not exceed the value set in the property file.upload.size.max.bytes in the Panopticon.properties.

Steps:

1. Right-click on a folder and select **Import Bundle** on the context menu.



The Import Bundle dialog displays.



- 2. To import a bundle, you can either:
 - Drag it from your desktop and drop on the dialog, or
 - Click Choose Bundle to Import and select one on the Open dialog that displays.

The name of the selected bundle is displayed on the dialog box.



3. Check the **Keep Folder Structure** box.

This means the exported folder structure is maintained when uploading the bundle. If the folders do not exist on the server, they will be created.

4. To replace an existing workbook, check the **Replace existing workbook** box.




Data Level Secure Access

In this case the data being displayed is filtered to a particular authenticated user.

Data is filtered using the special parameter _user_id.

This _user_id parameter is replaced at run time by the authenticated user id in lower case.




This parameter can then be used to restrict the data being retrieved, though use in either:

- □ Connection Details to Data Sources
- ☐ Filter constraints on data queries (e.g., SQL WHERE Clauses)

[7] SYSTEM ADMINISTRATION

Panopticon Real Time system administration is done on the following pages of the System tab:



Page	Description
System Settings	Allows to view the license and server information.
Subscriptions	Allows to view and manage real-time plugin subscriptions.
Caches	Allows to view, refresh, clear, or delete caches that are currently running on the server.
Logs	Allows to set the logging level and view logs. Also, pause or resume logging, and copy or clear logs.
Scheduler	Allows scheduling of email send outs and extracting of data.
Logged In User	Allows to view and manage logged in users.
<u>API Tokens</u>	Allows to add, delete, and view API Tokens.
<u>Fonts</u>	Allows to add custom fonts that can be used in a part or workbook.

SYSTEM SETTINGS


	_							
The	Svstem	Settings	page	include	the	following	panes o	r sections:

- ☐ <u>License Information</u>
- Server Information


View License Information

If the licensing used is Altair Units license, the following license information are displayed:

- License server type
- License version
- Start Date and End Date of the license
- □ Total number of units available in the license



If the <u>licensing</u> used is the volume-based XML file (named **PanopticonLicense.xml**), the content and location (i.e., /etc/panopticon/appdata) of the license are displayed.



View Panopticon Real Time Information


On the System Settings page, the following server information are displayed:

Server Property	Description
Operating System	The server host operating system.
Java Version	The version of the Java Runtime Environment.
Java Vendor	The vendor of the Java Runtime Environment.
Tomcat	Identifies the Tomcat hosting the server
Tomcat Version	The Tomcat version.

Tomcat Memory (Mb)	The total amount of memory available to the Java Virtual Machine.
Max Memory (Mb)	The maximum amount of memory that the Java Virtual Machine will attempt to use.
Free Memory (mb)	The amount of free memory in the Java Virtual Machine.
Available Cores	The number of cores available to the Java Virtual Machine.
Uptime	The time when Panopticon Real Time was last started.

VIEW PLUGIN SUBSCRIPTIONS

View all of the currently running real-time plugin subscriptions.



Including the following information:


- □ Data source with an installed plugin
- Workbook name
- Data table name
- ☐ Current size of the real-time table held by the plugin such as number of rows and columns

For subscriptions created by ad hoc services, or those with no owner (workbook reference), they can be viewed on the *Preview Subscriptions* section.

You can also opt to do any of the following:


☐ Click Cancel All

to cancel all of the subscriptions on the Subscriptions section.



Cancel a plugin subscription by clicking X
 A notification message displays.

Cancel all






Move to other pages

WORKING WITH CACHES

On the Caches page, you can view, refresh, or delete caches that are currently running on the server.




The Caches list includes the following information:


	Cache rendering type
	Workbook Name
	Data Table Title
	Data Source Name
	Read Count
	Cell Count
	Cache Age
	Time to Live (Expires In)
	Response Length
You	can also do the following
	Display Data Table Cacl

- Display Data Source Cache
- Display Query Cache


Select a Cache Type to display in the list.




Data Table Cache Type



Data Source Cache Type



Query Cache Type




Refresh page



Delete individual caches

Select the checkbox of a cache or several caches, then click Delete. A notification displays.





■ Move to other pages

VIEW LOGS


View the latest 300 rows of a *Logging Level* in the **Logs** tab:

- FINEST (lowest level)
- ☐ FINER
- □ FINE
- CONFIG
- INFO (default level)
- WARNING

SEVERE (highest level)


Steps:


1. On the System page, click the Logs tab. Initially, the default level (INFO) logs are displayed.



2. Select another Logging Level in the drop-down.

For example, FINEST.






The latest 1000 rows of the selected log level or higher are fetched.


- 3. You can also click any of the following buttons:
 - to pause the logging, it changes to
 - to resume the logging
 - to copy log to clipboard
 - to clear the logs

SCHEDULING TASKS

On the Scheduler tab of the System Settings page, Panopticon Real Time allows scheduling of tasks.



A new scheduled task is added to the list with the properties.




Scheduler Property	Description
1	Run Task Manually run scheduler task.
2	Upload Task Upload scheduler task.
3	New Task Create a new scheduler task.
4	Delete Task Delete a scheduler task.
5	Download Task Download a scheduler task.
6	Task Properties The task properties include: Name of the task Activated status Type of the scheduled task Trigger type: Period or CRON Last user who made an update Date/Time when the task was created Date/Time when the task was last ran Last run result: Success or Failed For failed results, you can hover on the tooltip to view the error. NOTE: The result is not displayed for Extract Data scheduler type.

+ New Task

To create a new task, click **New Task** the following tasks:

. The $\textit{New Task}\xspace$ pane displays that allows you to define



Extracting Data



To allow scheduling of email send outs, Panopticon Real Time must be configured with valid email server information in the Panopticon.properties file located in the AppData folder (e.g., /etc/panopticon/appdata).

See Panopticon Real Time Configurations for Email Send Outs and Alerts for instructions.


 If any data load fails, such as when the data source is offline, the PDF/Image generation fails as well, and an email will not be sent.

Creating Task to Clear and Import Data Table to Data Store

Allows you to clear the earlier imported data and import again to the data store.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 2. Tap the Activated slider to turn it on.
- 3. Select the Trigger. You can either select:
 - · Period then enter the Interval (in seconds), or



• **CRON** then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)



- 4. Select the task Type: Data Store Clear and Import.
- 5. Enter the Description of the task.
- 6. Select the Data Table Name that will be cleared in the data store and imported again.




- Once saved, you can opt to click
 Run
 to manually run the task.
- Click to go back to the *Tasks* pane. A new task is added to the list.

Creating Task to Import Data Table to Data Store

Allows you to store data closer to Panopticon server in an embedded database.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 2. Tap the Activated slider to turn it on.
- 3. Select the Trigger. You can either select:
 - Period then enter the Interval (in seconds), or



• **CRON** then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)



- Select the task Type: Data Store Import Data.
- 5. Enter the Description of the task.
- 6. Select the Data Table Name that will be imported in the data store.




- Once saved, you can opt to click to manually run the task.
- Click to go back to the *Tasks* pane. A new task is added to the list.

Creating Task to Send CSV Data via Email

Panopticon Real Time provides the functionality to create tasks to generate and email CSV data from a workbook, dashboard, or visualization.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 2. Tap the Activated slider to turn it on.
- 3. Select the Trigger. You can either select:
 - Period then enter the Interval (in seconds), or



- 4. Select the task Type: Email CSV Data.
- 5. Enter the *Description* of the task.
- 6. Upon selecting Email CSV Data, the Scheduler page changes to allow specification of the following:
 - Select the Workbook Name in the drop-down list. These are the published workbooks available on the Workbooks page.

You can also enter the workbook name in the *Search* box. For workbooks in folders, ensure to start with \to include folder names.

 Select dashboards or parts where to source the CSV data from, by checking their corresponding boxes in the Dashboards & Parts drop-down list.

Dashboards & Parts	Industry Performance by Region, Regional Performa
Parameter Values Output File Names	☐ How To Actions ✓ Industry Performance by Region ✓ Regional Performance ✓ Industry Performance
Zip CSV Data	Navigation Target
Email	Scatter of Filtered Universe for {Region: Action Controls - Single Value
To ②	Action Controls - Single value
cc ③	Numeric Range Action Controls - Form
BCC ②	Action Controls - Datetime
Subject	☐ Data Entry ✓ Treemap1
Body	☐ Time Parameters ✓ Start: {TWS: yyyy-MMM-dd} End = {TW
	Data-driven Parameters

You can also opt to enter the Parameter Values that will be added as parameters to the subject line of
emails or as dashboard values in the CSV Data.

Such as Parameter=Value, and are comma separated. For example:

Region=Europe, Industry=Financials

NOTE

- See <u>Setting Parameter Values in Scheduler Tasks</u> for more information on the different syntax you can use to enter parameters with multiple values, as well as parameter values that contain comma.
- The following Date/Time range querying parameters are also supported in the Email CSV Data task:
 - CurrentTime
 - LastWorkDay
 - WeekStart
 - QuarterStart

For example:

{CurrentTime:dd-MMM-yyyy}

However, when there is no Date/Time format supplied, the default format yyyy-MM-dd will be used instead.

Enter comma-separated list of Output File Names.

NOTE

- The items in the list must be either unique or empty.
- Empty string items indicate that the default title should be used.
- By default, the text box is blank causing the implicit naming to be used.
- If the supplied names are fewer than the selected data sets, the default naming comes into effect for non-specified names.
- 7. You can opt to tap the **Zip CSV Data** slider to attach a zipped copy of the CSV data in the email.
- 8. Enter the email address of the recipient in the To field.
- 9. You can opt to enter the following:
 - Sender Name alias to use when sending email. If left blank, the value of email.sender_name property in Panopticon.properties will be used.
 - CC and/or BCC recipients of the email separated by a comma.
 - The mail message subject to be used in the email notifications in the Subject field.

NOTE Supports dashboard parameters.

The content of the email in the Body box.



Once saved, you can opt to click



to manually run the task.


• Click to go back to the *Tasks* pane. A new task is added to the list.

Creating Task to Send an MS Excel File via Email

Panopticon Real Time provides the functionality to create tasks to generate and email MS Excel files.


Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 2. Tap the Activated slider to turn it on.
- 3. Select the *Trigger*. You can either select:
 - Period then enter the Interval (in seconds), or



• **CRON** then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)



4. Select the task *Type*: **Email Excel**.

Upon selecting **Email Excel**, the *Scheduler* page changes to allow specification of the following:

- Enter the Description of the task.
- Select the Workbook Name in the drop-down list. These are the published workbooks available on the Workbooks page.

You can also enter the workbook name in the *Search* box. For workbooks in folders, ensure to start with \ to include folder names.

 Select the dashboards to include in the MS Excel file by checking their corresponding boxes in the Dashboards drop-down list.

NOTE Multiple tables per dashboard are inserted in a sheet of the MS Excel file.

- 5. You can also opt to:
 - Enter the Parameter Values that will be added as parameters to the subject line of emails or as dashboard values in the MS Excel file

Such as Parameter=Value, and comma separated. For example:

Region=Europe, Industry=Financials

NOTE

- See <u>Setting Parameter Values in Scheduler Tasks</u> for more information on the different syntax you can use to enter parameters with multiple values, as well as parameter values that contain comma.
- The following Date/Time range querying parameters are also supported in the Email CSV Data task:
 - CurrentTime
 - LastWorkDay
 - WeekStart
 - QuarterStart

For example:

{CurrentTime:dd-MMM-yyyy}

However, when there is no Date/Time format supplied, the default format yyyy-MM-dd will be used instead.

- check the Hide Scrollbars box.
- 6. Enter the Width and Height of the MS Excel file. Default values are 1024px and 768px, respectively.
- 7. Enter the Table Style. The default is TableStyleLight1.
- 3. Select one of the following *Modes*:
 - Images and Data Table Images and data are exported to the Excel file (default).
 - Data Only the data is exported to the Excel file.

NOTE

Supported visualizations include Table, Heat Matrix, and Record.

- 9. Enter the email address of the recipient in the *To* field.
- 10. You can opt to enter the following:
 - Sender Name alias to use when sending email. If left blank, the value of email.sender_name property in Panopticon.properties will be used.
 - CC and/or BCC recipients of the email separated by a comma
 - The mail message subject to be used in the email notifications in the Subject field

NOTE

Supports dashboard parameters.

Content of the email in the Body box



11. Click

- Once saved, you can opt to click

 Run
 to manually run the task.
- Click to go back to the Tasks pane. A new task is added to the list.

Creating Task to Send an HTML Formatted Data via Email


Panopticon Real Time provides the functionality to create tasks to generate and email HTML-formatted table exported from a selected workbook and dashboards.

IMPORTANT

Use it with caution! When emailing HTML formatted data, the email message size runs the risk of becoming very large if the data used in the visualization is too large and/or complex. The data volume will not stop Panopticon Real Time from creating the message and the HTML-formatted data, but email servers may struggle to send and/or receive the message.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 3. Tap the Activated slider to turn it on.
- 4. Select the Trigger. You can either select:
 - Period then enter the Interval (in seconds), or



• **CRON** then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)



5. Select the task *Type*: Email HTML Formatted Data.

Upon selecting **Email HTML Formatted Data**, the *Scheduler* page changes to allow specification of the following:

- Enter the Description of the task.
- Select the Workbook Name in the drop-down list. These are the published workbooks available in the Workbooks page.

You can also enter the workbook name in the *Search* box. For workbooks in folders, ensure to start with \ to include folder names.

 Select the dashboards and parts to include in the HTML formatted data file by checking their corresponding boxes in the Dashboards & Parts drop-down list. 6. You can also opt to enter the Parameter Values that will be added as parameters to the subject line of emails or as dashboard values in the MS Excel file.

Such as Parameter=Value, and are comma separated. For example:

Region=Europe, Industry=Financials

NOTE

- See Setting Parameter Values in Scheduler Tasks for more information on the different syntax you can use to enter parameters with multiple values, as well as parameter values that contain comma.
- The following Date/Time range querying parameters are also supported in the Email CSV Data task:
 - CurrentTime
 - LastWorkDay
 - WeekStart
 - QuarterStart

For example:

{CurrentTime:dd-MMM-yyyy}

However, when there is no Date/Time format supplied, the default format yyyy-MM-dd will be used instead.

- 7. Enter the email address of the recipient in the *To* field.
- 8. You can opt to enter the following:
 - Sender Name alias to use when sending email. If left blank, the value of email.sender name property in Panopticon.properties will be used.
 - CC and/or BCC recipients of the email separated by a comma.
 - The mail message subject to be used in the email notifications in the Subject field.

Supports dashboard parameters. NOTE

The content of the email in the Body box.



- Once saved, you can opt to click
- Run to manually run the task.
- to go back to the Tasks pane. A new task is added to the list.

Creating Task to Send Image File via Email

Panopticon Real Time provides the functionality to create tasks to generate and email Image files.


In addition, hyperlinks can also be used in email dashboard images. Hyperlinks can redirect to a workbook and a dashboard in the server.



See the Email Data: Image section for more information.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 2. Tap the Activated slider to turn it on.
- 3. Select the Trigger. You can either select:
 - Period then enter the Interval (in seconds), or



CRON then enter a CRON Expression on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)



4. Select the task *Type*: **Email Image**.


Upon selecting Email Image, the Scheduler page changes to allow specification of the following:

- Enter the Description of the task.
- Select the *Workbook Name* in the drop-down list. These are the published workbooks available in the *Workbooks* page.

You can also enter the workbook name in the *Search* box. For workbooks in folders, ensure to start with \ to include folder names.

 Select dashboards or parts to include in the image file by checking their corresponding boxes in the Dashboards & Parts drop-down list.

Inline Image




The selected dashboards or parts are inserted as parameterized text and inline images in the Body edit box.



Clicking the **Preview** icon displays the image placeholders for the selected dashboards or parts.

Body ∅

{Candlestick_title}
{Candlestick_image}
{Cross Tab Pivot Table_visualization.Tile2_title}
{Cross Tab Pivot Table_visualization.Tile2_image}
{Cross Tab Pivot Table_visualization.Tile1_title}
{Cross Tab Pivot Table_visualization.Tile1_image}
{Donut Gauge_visualization.DonutGauge2_title}
{Donut Gauge_visualization.DonutGauge2_image}
{Donut Gauge_visualization.DonutGauge1_title}
{Donut Gauge_visualization.DonutGauge1_image}



 Select bookmarks in the workbook to include in the image file by checking their corresponding boxes in the Bookmarks drop-down list.

5. You can also opt to:

 Enter the Parameter Values that will be added as parameters to the subject line of emails or as dashboard values in the Image file

Such as Parameter=Value, and are comma separated. For example:

Region=Europe, Industry=Financials

NOTE

- See <u>Setting Parameter Values in Scheduler Tasks</u> for more information on the different syntax you can use to enter parameters with multiple values, as well as parameter values that contain comma.
- The following Date/Time range querying parameters are also supported in the Email CSV Data task:
 - CurrentTime
 - LastWorkDay
 - WeekStart
 - QuarterStart


For example:

{CurrentTime:dd-MMM-yyyy}

However, when there is no Date/Time format supplied, the default format yyyy-MM-dd will be used instead.

- Enter the Width and Height of the Image file. Default values are 1024 and 768, respectively.
- Select the Hide Scrollbars checkbox.
- Select the Hyperlinks checkbox. This makes the Image file in the email will be clickable.
- Enter the email address of the recipient in the To field.

- 7. You can opt to enter the following:
 - Sender Name alias to use when sending email. If left blank, the value of email.sender name property in Panopticon.properties will be used.
 - CC and/or BCC recipients of the email separated by a comma.
 - The mail message subject to be used in the email notifications in the Subject field.



The content of the email in the Body box.




- Run Once saved, you can opt to click to manually run the task.
- to go back to the Tasks pane. A new task is added to the list.

Creating Task to Send PDF File via Email

Panopticon Real Time provides the functionality to create tasks to generate and email PDF files.

Steps:

- On the New Task pane, enter the Name of the task. Ensure the name is unique.
- Tap the Activated slider to turn it on.
- Select the *Trigger*. You can either select:
 - Period then enter the Interval (in seconds), or



CRON then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)



- 5. Select the task *Type*: **Email PDF**.
- Upon selecting **Email PDF**, the *Scheduler* page changes to allow specification of the following:
 - Enter the *Description* of the task.
 - Select the Workbook Name in the drop-down list. These are the published workbooks available on the Workbooks page.

You can also enter the workbook name in the *Search* box. For workbooks in folders, ensure to start with \ to include folder names.

- Select dashboards to include in the PDF by checking their corresponding boxes in the Dashboards dropdown list.
- Select bookmarks in the workbook to include in the PDF by checking their corresponding boxes in the Bookmarks drop-down list.
- 8. You can also opt to:
 - Enter the *Parameter Values* that will be added as parameters to the subject line of emails or as dashboard values in the PDF file.

Such as Parameter=Value, and are comma separated. For example:

Region=Europe, Industry=Financials

NOTE

- See <u>Setting Parameter Values in Scheduler Tasks</u> for more information on the different syntax you can use to enter parameters with multiple values, as well as parameter values that contain comma.
- The following Date/Time range querying parameters are also supported in the Email CSV Data task:
 - CurrentTime
 - LastWorkDay
 - WeekStart
 - QuarterStart

For example:

{CurrentTime:dd-MMM-yyyy}

However, when there is no Date/Time format supplied, the default format yyyy-MM-dd will be used instead.

- Select the **Enable Pagination** checkbox.
- Select the Hide Scrollbars checkbox.
- 9. Enter the email address of the recipient in the *To* field.
- 10. You can opt to enter the following:
 - Sender Name alias to use when sending email. If left blank, the value of email.sender_name property in Panopticon.properties will be used.
 - CC and/or BCC recipients of the email separated by a comma.
 - The mail message subject to be used in the email notifications in the Subject field.

NOTE

Supports dashboard parameters.

• The content of the email in the Body box.



11. Click

- Once saved, you can opt to click


 Run
 to manually run the task.
- Click to go back to the Tasks pane. A new task is added to the list.

Creating Task to Extract Data

Tasks can be created to reload workbooks or global extracts.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 2. Tap the Activated slider to turn it on.
- 3. Select the Trigger. You can either select:
 - Period then enter the Interval (in seconds), or




• **CRON** then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI).



- 4. Select the task *Type*: **Extract Data**.
- 5. Enter the Description of the task.
- 6. Select the data extract to be scheduled in the *Extract Name* drop-down list box. The list is taken from the data extracts list on the *Extracts* tab.



- Once saved, you can opt to click
 Run
 to manually run the task.
- Click to go back to the *Tasks* pane. A new task is added to the list.

Setting Parameter Values in Scheduler Tasks

Use any of the following syntax to define parameter values in scheduler tasks:

☐ For multiple values (array parameter), use bracket syntax

Example: parameter1=[Value1, Value2, Value3]

☐ For a parameter with a value containing comma, quote the value in double quotes

Example: parameter1="Parameter value, containing comma"

☐ The double quoting can also be used inside arrays

Example: parameter1=[Value1, "Value2, containing comma"]

Normal parameters, quoted parameters, and array parameters can be mixed

Example: parameter1=Normal, parameter2=[Val1, Val2], parameter3="Quoted Value"

Uploading a Scheduler Task


Users with an Administrator role can upload scheduler task definitions.

Steps:

1. On the **Scheduler** tab, click **Upload**




The Upload Task dialog displays.




- 2. To upload a task, you can either:
 - · Drag it from your desktop and drop on the dialog, or
 - Click Choose task to upload and select one on the Open dialog that displays.

The name of the task is displayed on the uploaded task area and in the *Name* box.



- 3. You can opt to rename the task.
- 4. To replace an existing task, check the Replace task box.
- 5. Click Upload

You will be notified once the task is uploaded.



The task is added and displayed in the Scheduler list.

Downloading a Scheduler Task

Users with an Administrator role can download scheduler task definitions.

Click the **Download** icon of a task.

Other Scheduler Tasks Operations

On the **Scheduler** tab of the *System Settings* page, you can also perform the following:

Sort tasks

A task displays the following columns: Name, Activated, Type, Trigger, Last Updated By, Created, and Last Run.

Modify the sorting of the list by clicking the $\stackrel{\downarrow}{}$ or $\stackrel{\uparrow}{}$ button of any of these columns. The icon beside the column that was used for the sorting will indicate if it was in ascending or descending order.


Manually run tasks

Instead of waiting for the set Period interval or CRON Expression, you can manually execute the task by clicking

The Last Run and Last Run Result (Success or Failed) are displayed. For failed results, you can hover on the tooltip to view the error.

- Modify tasks
- Delete tasks

Click of a task. A confirmation message displays.



Modify a Scheduled Task

Steps:

- On the **Scheduler** tab, click the link of a task to modify.
 The properties of the task are displayed.
- 2. Apply the desired changes.



MANAGING PANOPTICON REAL TIME USERS

Users with an Administrator role can view the logged in users on Panopticon Real Time and log them out when necessary. The ability to manage users is beneficial in monitoring the utilization of Altair Units license.


On the **Logged In Users** tab of the *System* page, Administrators can perform the following:

View	logged	in	users

- □ Sort logged in users
- Log out users
- Refresh the Logged In Users list

Viewing Logged In Users

On the System page, click the Logged In Users tab. The list of logged in users is displayed.



In the list, the following properties are displayed for each user:

Property	Description
Username	Username used to the login to Panopticon Real Time.
Roles	Roles assigned to the user.
Login Time	The Date/Time the user logged in.
Active Sessions	The number of tokens a user is using. For example, if the user is logged in from two different computers, he will have two active sessions. However, if the user has two tabs on one computer, they will share a token and the active sessions will be one.
Designing	Indicates if a logged in user is currently designing a workbook.

Sorting Logged In Users

Sorting the logged in users can be done through the Username, Login Time, or Active Sessions column name.

Steps:

- 1. On the System page, click the Logged In Users tab. The list of logged in users is displayed.
- 2. Click on the Username, Login Time, or Active Sessions column header then click the Sort Order.
 - Ascending
 - Descending

Logging Out Users

Logging out users on the server consequently deletes their tokens.

Logging Out All Users

Steps:

1. Click

Altair Panopticon Workbooks Data Library Webhooks Alerts Parameters Themes System Logged In Users System Settings B Logout all Subscriptions Username ↑ **Login Time Active Sessions** Designing Caches admin ANONYMOUS, Viewer, Administrator Oct 19, 2021 1:12 PM \Rightarrow Logs ANONYMOUS, Viewer, Designer Oct 19, 2021 1:11 PM \Box Scheduler designer Logged In Users API Tokens Fonts


A notification message displays.



2. Click Yes

Except for the user (i.e., admin) who is calling out the logging out of the other users, all of the other users are logged out.


Also, the button of admin is disabled.



Logging Out Individual Users

Steps:

Click the button of a user in the list.
 A notification message displays.



2. Click Yes

The user is logged out and their token is deleted.

Refreshing the Logged In Users List


Click to refresh the list of logged in users.

MANAGING API TOKENS


On the API Tokens page, an Administrator user can add API Tokens that returns a key used for authorizing requests to the server.


Steps:






- 2. Enter the Label.
- 3. Click . The New API Token Created dialog displays with the auto-generated key.





- 4. Click to ensure you have a copy of the key and paste in a secure location.
- 5. Click . The new API Token is displayed on the list.




In the list, the following properties are displayed for each API Token:

Property	Description
Label	Label of the API Token. NOTE: Select a label that is easy for you to remember.
Created By	The user who created the API Token. NOTE: Only Administrator users can create API Tokens. However, the keys can be used by anyone as long as they are not revoked.
Last Accessed	Date/Time when the API Token was last accessed.

Click on any of these column headers then click the Sort Order to sort the list.


- Ascending
- Descending

You can also opt to click to remove and revoke the API Token from the server.



ADDING CUSTOM FONTS

Users with an Administrator role are allowed to add fonts on the System tab in Panopticon Real Time.



The supported custom font files include the following:


☐ ttf

otf

When available on the server, the client will automatically detect and load the font and consequently, can be used in a part or workbook. Otherwise, the client will fall back to the system installed fonts.

Steps:

+ Add FontsThe Add Fonts dialog displays.




2. To add fonts, you can either:

- drag them from your desktop and drop on the dialog, or
- click **Choose Fonts** and select one or more fonts on the *Open* dialog that displays.


The names or the number of fonts is displayed on the uploaded font area.






3. Click Upload


A notification prompt will be displayed once the fonts are uploaded.



The added custom fonts are displayed on the Fonts page.



Click



[8] CONNECTIVITY AND INTEGRATION

THIRD PARTY SOFTWARE DEPENDENCY INSTALLATION

Some data connectors require additional third-party software installation to be enabled which typically requires adding JAR files to the Lib folder of the Tomcat installation and then restarting Tomcat.

Common additions include:

	1	Г	D	\sim		۱riر	,,	ro
ч .	J	u	D	$\overline{}$	u	יו וי	ſυ	ıs

■ Advanced Message Processing System (AMPS)

The latest version for AMPS can be downloaded from the 60East Technologies official website: http://www.crankuptheamps.com/amps/

Copy amps_client.jar, amps_client-javadoc.jar and amps_client-sources.jar into the Tomcat lib folder.

The pre-compiled JAR files are in the api\client\java\dist\lib\ directory, which contains the JAR files mentioned above.

All of the above-mentioned java dependency files can be found after downloading and installing the AMPS Java Evolution Kit.

If a user has Linux machine available, install the AMPS distribution. Otherwise, download the AMPS Evolution Virtual Machine.

NOTE

To effectively use the .jar files, unblock these files by right-clicking on the File and selecting **Properties**. On the **General** tab, click **Unblock**.

Elasticsearch connector

Dependencies for Elasticsearch are included in Panopticon Real Time installation.

Select the target Elasticsearch version and unzip the contents of the appropriate dependency zip into the Tomcat lib folder.

☐ JMX

Use the following java options to enable JMX monitoring for the JMX plugin:

Enable JMX remote connection: (-Dcom.sun.management.jmxremote)

Disable JMX authentication: (-Dcom.sun.management.jmxremote.authenticate=false)

Set remote port for jmx: (-Dcom.sun.management.jmxremote.port=number)

NOTE

Providing invalid parameters into JMX connection string may cause a number of exceptions and make the server inaccessible. Make sure you are using the syntax provided above.

OneMarketData OneTick / OneTick CEP

This connector requires that the following JAR be added:

jomd.jar

Which is retrieved from the OneTick bin folder:

For example:

C:\omd\one market_data\one_tick\bin

Additionally, the following environment variables **MUST** be configured:

PATH

To include the OneTick bin folder.

For example:

C:\omd\one market data\one tick\bin

ONE_TICK_CONFIG

To reference the OneTick configuration file.

For example:

C:\omd\client data\config\one tick config.txt

Plus, the Tomcat configuration should include the following Java option:

```
-Djava.library.path=C:\omd\one_market_data\one_tick\bin
```

The OneTick configuration file should have entries for Windows OS time zone mapping and information.

Example:

```
WINDOWS_TZ_MAPPING_FILE="C:/OMD/one_market_data/one_tick/config/windows_tz
   mapping.dat"
```

```
WINDOWS_ZONEINFO_PATH="C:/OMD/one_market_data/one_tick/config/zoneinfo"
```

Additionally, the OneTick client folder should be set to have the same permissions as those running the Tomcat process. Please check that the OneTick Java API is operational, before accessing workbooks through the server that utilize OneTick connectivity. This can be easily achieved by running one of the OneTick Java API examples.

NOTE

- The OneTick JAR must be updated to match the version of the OneTick client installation.
- For version 16.7.0, the OneTick connector is built and tested against version 1.17 of the OneTick Client.

SAP Sybase ESP

Manually copy the following dependency files from the Sybase ESP installation folder (e.g., C:\Sybase\ESP-5 1\libj):

- commons-codec-1.3.jar
- log4j-1.2.16.jar
- streaming-client.jar
- streaming-system.jar
- ws-commons-util-1.0.2.jar
- xmlrpc-client-3.1.3.jar
- xmlrpc-common-3.1.3.jar

NOTE

Make sure the dependency files are copied to the appropriate ${\tt WEB-INF}$ folder in Apache Tomcat:

- For 64-bit: C:\Program Files\Apache Software
 Foundation\Tomcat 9.0\webapps\panopticon\WEB-INF\lib
- For 32-bit: C:\Program Files (x86)\Apache Software Foundation\Tomcat 9.0\webapps\panopticon\WEB-INF\lib

StreamBase CEP

This connector requires the following JAR to be added:

sbclient.jar

Which is retrieved from the StreamBase Lib folder.

For example: C:\TIBCO\sb-cep\7.5\lib

■ StreamBase LiveView

This connector requires the following JAR files to be added:

• sbclient.jar, lv-client.jar, lv-client-wwwdeps.jar

Which are retrieved from the StreamBase Lib folder.

For example: C:\TIBCO\sb-cep\7.5\lib

Plus, the JARS from the LiveView installation:

• lv-compiler.jar,jyaml-1.3.jar

Which are retrieved from the LiveView Lib folder.

For example: C:\TIBCO\sb-cep\7.5\liveview\lib

DATABASE

There are two ways of connecting to a database from Panopticon Real Time.

a. Use the Listed Data Connector for the specific Database (if available).

Includes: Cassandra, Elasticsearch 7.x, InfluxDB 1.x, Kx kdb+, ksqlDB, MongoDB, OneTick, Panopticon Data Extract.

b. Use the JDBC connector.

This requires:

- 1. Addition of the JDBC JAR(s) for the required Database into Tomcat/Lib.
- 2. For JNDI:

Update of the server configuration file: panopticon.xml to include the new JNDI resource name.



 For URL: Use the <u>URL</u> specific to the database's JDBC driver, the <u>Driver Class Name</u> specific to the driver, and the <u>Username</u> and <u>Password</u>.



JDBC Driver Installation

Install the relevant JDBC driver(s) on the system where you are running Tomcat and Panopticon Real Time. The exact installation procedure depends on the JDBC driver. Follow the instructions given by the provider of the JDBC driver and by the provider of your Java application server (for example, Apache Tomcat). In almost every case, a JDBC driver is installed by placing one or several jar-files in the lib folder of your Tomcat installation.

JNDI Connection Details

JNDI Connection details are specified in Panopticon Real Time configuration file panopticon.xml.

Each connection has the following structure:

```
<Resource name="jdbc/[Unique Name]"
    auth="Container"
    type="javax.sql.DataSource"
    maxActive="100"
    maxIdle="30"
    maxWait="10000"
    username="[User Name]"
    password="[Password]"
    driverClassName="[Class Name]"</pre>
```

```
wrl="[URL]"

/>

Where:

Unique Name: Defines the unique JNDI resource name to be used.

User Name: The username to authenticate to the database.

Password: The password to authenticate to the database.

Class Name: The Class Name specific to the Database's JDBC Driver.

URL: The URL specific to the Database's JDBC Driver, and selected Server instance and database.

Additionally, other key attributes of the JNDI resource are:

maxActive: The maximum number of active connections that can be allocated from this pool.

maxIdle: The maximum number of connections that will be kept active even when there are no requests.

maxWait: Maximum time in milliseconds to wait for a database connection to become available.
```

Encrypted Password for JNDI Resource

The database password in a JNDI Connection can optionally be encrypted, to avoid having the password saved in clear text in the panopticon.xml file. This requires the following:

- ☐ The PanopticonJNDIDataSourceFactory.jar from the Panopticon distribution zip archive must be placed in the tomcat/lib folder
- ☐ The clear text password must be encrypted using PCLI and the Encrypt command
- The special factory .JAR file must be specified in the Resource definition (see example below)

This is an example of a JNDI Connection Resource tag in panopticon. xml when using an encrypted password. The example assumes that a MonetDB database is used.

```
<Resource name="ds_secure"
  factory="com.panopticon.server.jndi.ds.SecureTomcatDataSourceFactory"
  auth="Container"
  type="javax.sql.DataSource"
  maxActive="100"
  maxIdle="30"
  maxWait="10000"
  username="monetdb"
  password="7QdcwxTWuj+moJPZiFXquQ=="
  driverClassName="org.monetdb.jdbc.MonetDriver"
  url="jdbc:monetdb://1.2.3.4:50000/altair"/>
```

Common Databases and their JNDI Configurations

Database	Description
Oracle 11	<pre>Using ojdbc6.jar driverClassName="oracle.jdbc.OracleDriver" url="jdbc:oracle:thin:@[HostName]:1521:[DatabaseName]"/></pre>
MS SQL Server	<pre>Using sqljdbc4.jar driverClassName="com.microsoft.sqlserver.jdbc.SQLServerDriver" url="jdbc:sqlserver://[Server]\[Instance];databaseName=[Database Name]"/></pre>
Sybase ASE	<pre>Using jconn4.jar driverClassName="com.sybase.jdbc4.jdbc.SybDriver" url="jdbc:sybase:Tds:[HostName]:5000/[DatabaseName]"</pre>
PostgreSQL	<pre>Using postgresql-9.4.1208.jar driverClassName="org.postgresql.Driver" url="jdbc:postgresql://[HostName]:5432/[DatabaseName]"</pre>
MySQL	<pre>Using mysql-connector-java-5.1.38-bin.jar driverClassName="com.mysql.jdbc.Driver" url="jdbc:mysql://[HostName]:3306/[DatabaseName]"/></pre>

R AND PYTHON TRANSFORM SUPPORT

R and Python connectivity and transforms occur over TCP/IP network links.

- For R, Rserve is used.
- ☐ For Python, FastAPI is the recommended integration method for Linux systems, while Pyro4 (Python Remote Data Objects) can be used on either Windows or Linux.

R Integration

To enable R connectivity:

- 1. Download R, install it, and the R Console (http://cran.rstudio.com/).
- 2. Open the R Console.
- 3. Install Rserve using the following command from within the R Console:

```
install.packages("Rserve")
```

4. Initiatiate the Rserve library using the following command:


library(Rserve)

5. Run Rserve by executing the following command:

Rserve()

Only steps 2, 4 & 5 need to be repeated when R connectivity is required.

Example:



NOTE Connectivity by default is over Port 6311.

To enable authentication across the Rserve TCP/IP link

create a password file (pwdfile.pwd)

Each line of the file should have the user and then the password.

Example:

```
user1 password1
user2 password2
```

auth required

☐ Create a configuration file with following parameters (rconfig.conf)

```
pwdfile [path of password file]

Example:

remote enable
auth required
port 6311
pwdfile C:\\RIntegration\\pwdfile.pwd
```

load the created configuration file (the default Rserve configuration file is still loaded, but its settings have lower priority) and run Rserve:

```
Rserve(args="--RS-conf [path of configuration file]")
Example:
Rserve(args="--RS-conf C:\\RIntegration\\rconfig.conf")
```

Python Integration with Pyro4

Panopticon can use Python for both data transforms and as a primary data source. The server part of Panopticon will send requests to Python, with data and/or Python code, via Pyro4 - Python Remote Objects. Pyro4 installs as a Python package in your Python environment, and connectivity is enabled by starting a Pyro process with a shell script file (.BAT script file) which is included in the Panopticon distribution zip-archive.

To set up a Python environment that can be used from Panopticon, follow these steps:

- 1. Download and install Python.
- 2. Install Pyro4.
- 3. Install pandas.
- 4. Install additional packages.
- 5. Set the Pyro HMAC key.
- Start Pyro4.

Downloading and Installing Python

Download Python from https://www.python.org/downloads/ and select the release version you require as well as the right version for the operating system of your server. Note that Linux systems often have Python included out of the box. Install Python as described by documentation from Python.org. You can install Python on the same host that runs the Panopticon server, or a different host, if firewall settings and port mapping allow communication between the two hosts. If you are running Panopticon for development, testing or personal use on your workstation, install Python on your workstation as well.

Installing Pyro4

When Python is installed, add Pyro4 by installing it like a Python package. The Pyro4 version must be 4.71 or higher. On the command prompt, type **python** and press **Enter** to start a Python prompt. Then run this command:

```
pip install Pyro4>=4.71
```

Installing Pandas

When working with a data table in Python, the pandas package and the pandas DataFrame object provides many useful advantages and is highly recommended. Panopticon's integration with Pyro4 will check if the object returned from Python is a pandas DataFrame and therefore the pandas package is required. On the Python prompt, run this command:

```
pip install pandas>=1.1.5
```

This will also automatically give you the NumPy package.

Installing Additional Packages

To be able to view and use the examples in the Panopticon example workbook "How to Python", you are also required to install a few additional packages using these commands:

pip install scikit-learn>=1.1.3
pip install pyarrow>=10.0.0

Setting the Pyro HMAC Key

When you send a request to Pyro4, you are required to supply the correct password which is called the Pyro HMAC Key. This password protects the Python environment from unauthorized remote calls via Pyro4. You should create an environment variable named PYRO_HMAC_KEY on the host where Python and Pyro4 are installed. However, if PYRO_HMAC_KEY is not found or created, the environment variable will be created by the script used for starting Pyro4. The default value is password. You have the option of either:

creating the PYRO_HMAC_KEY and setting a password value of your choice

editing the start script and entering your password value instead of the default value password

When using Python from Panopticon, either as a transform or as a primary data source, you will supply the password as part of the connection settings in Panopticon. The password can also be saved in the Panopticon.properties file, by an Administrator, which will let Designer users create Python connections without knowledge of the password.

For details about the configuration of Python connectivity properties, see Properties: Panopticon.

Starting Pyro4

Before you can use Python from Panopticon, you must start the Pyro4 process that will receive requests from Panopticon and pass them on to Python. This is done by running a script included with Panopticon on the host where Python and Pyro4 are installed.

On Linux, you run the file start_Python_connectivity.sh which in turn runs the file pyro.py.

On Windows, you run the file start_Python_connectivity.bat which in turn runs the file pyro.py.

Multiple Python Environments on Windows

On Windows, you can install multiple Python versions in parallel, resulting in installation folders like the following examples:

☐ C:\Program Files\Python38

C:\Program Files\Python39

□ C:\Program Files\Python310

Each of these versions has its own package installations. For example, you can have one version of a package installed for Python 3.9 and another package version for Python 3.10.

NOTE

When installing packages for different versions of Python on a host which will serve multiple users, make sure you install from a command prompt with elevated privileges (run As Administrator), otherwise, packages will be installed under your own Windows user profile folder.

With Python for Windows downloaded from Python.org, you also get py.exe which is a Python launcher. When installing Python for all users, it is placed in C:\Windows\py.exe or C:\Users\<username>\AppData\Local\Programs\Python.

With the Python launcher py.exe, you can start a specific Python version as follows:

```
py - 3.9
```

To make a package installation for a specific Python version, open a command prompt as Administrator and run:

```
py -3.9 -m pip install <packagename>
```

To start a Pyro4 process with a specific Python version (in this example, 3.9) you can launch Pyro4 as follows:

```
start Python connectivity.bat -3.9
```

Python Integration with FastAPI

On Linux OS, Panopticon can be integrated with Python using FastAPI instead of Pyro4.

Python integration with FastAPI has the advantage of supporting parallel processing.

Requirements:

- Python 3.8 or higher
- □ Python packages:
 - uvicorn >= 0.20.0
 - gunicorn >= 20.1.0
 - fastapi >= 0.88.0
 - pandas >= 1.5.1
 - serpent >= 1.41

Steps:

1. Copy the **panopticon fastapi py** folder to the host where you have your Python environment.

This can be the same host as where Panopticon is running, i.e., localhost from the point of view of Panopticon. If you are using different hosts, ensure that the firewall portmapping settings allow traffic on port **9090**.

You can place the folder to your preferred location.

2. Set the following values in the Panoption.properties file:

```
connector.python.host=<your_python_host>
connector.python.mode=fast_api
connector.python.port=9090
```

3. Restart Tomcat.

NOTE

 To start the FastAPI service, run the start.sh file with elevated privileges:

sudo ./start.sh

- To get back to the Linux prompt, hit Ctrl+Z (^Z) to pause the process and immediately run the command bg to send the process to the background.
- To shut down the FastAPI service, run the stop.sh file with elevated privileges:

sudo ./stop.sh

LOAD CUSTOM DATA PLUGINS

Panopticon Real Time will load a file named **Plugins.xml** during startup. The file contains class names of all the data plugins that will be loaded and applied to the server. However, the <code>Plugins.xml</code> file can be replaced in case the user wants to have a custom setup and load their own plugins or if they want to disable certain data plugins from being loaded. This is achieved by creating a new <code>plugins.xml</code> file and placing it in the <code>AppData</code> folder (e.g., <code>/etc/panopticon/appdata</code>).

The original plugins.xml file is always distributed with the panopticon.war file. From the .war file, copy the plugins.xml file from the root folder to your AppData (i.e., /etc/panopticon/appdata) folder. Then open plugins.xml and add or remove items to either enable or disable certain plugins.

NOTE

New data plugins are constantly being developed and distributed. Therefore, it is recommended that you revisit the shipped plugins.xml file after each release if you have replaced the default plugins.xml file.


[9] VIEWING AND MANAGING WORKBOOKS

ACCESSING WORKBOOKS


On the Recent tab of the Workbooks page lists available folders and uploaded or published workbooks in Grid View.

- ☐ The *Folders* include their names and the number of available workbooks.
- ☐ The Workbooks include their titles, thumbnail images, and when they were last modified.

Opened workbooks are then displayed on the Recent pane.




Clicking on the workbook thumbnail opens it on the web browser.





The signifies there are more dashboards in a workbook that can be opened. Click this icon to expand the drop-down list and display all of the available dashboards and select one to display.



Altair Panopticon Workbooks Data Library Webhooks Alerts Parameters Themes System ₼ Organization Q Search Workbook \equiv Name Orders Recent Shared **№ Users** ~admin\How to Auto Parameterize ~admin\How to Conflate Time Ser.. Folders Orders 20 2 workbooks Workbooks **Bond Maturity Screening** CrossTab **Displaying Spreads** Modified 12 days ago Modified 12 days ago Modified 12 days ago


On the **Shared** pane, the list of workbooks that are accessed through a shared link are displayed.

Searching for Workbooks

Search for particular workbooks that may be located in different folders and perform other operations like merge, copy, download, or remove.

Steps:


- On the Workbooks and Folders Summary layout, click on a workbook folder then enter a workbook name or dashboard name in the Search Workbook box.
- 2. Click →.



The following information are displayed for each workbook:

- Folder where the workbook is located
- What the search match was based on: workbook or dashboard name
- Date/Time when the workbook was last viewed
- Date/Time when the workbook was last modified

You can also enter one or more characters into the *Search Workbook* box then click **Enter**. The list of workbooks that matched the entries will be displayed.




Click on a workbook thumbnail to open and display it on the web browser.


To go back to the Workbooks and Folders Summary layout, click $\stackrel{\longleftarrow}{}$.




To display the context menu, you can either:

- Right-click on a workbook or several workbooks
- Click the **More Actions** icon of a workbook or selected workbooks






To display the workbook in its location, click **Show in Folder** on the context menu.





The other context menu options are discussed in the sections below.


Folders and Workbooks Display View

Workbooks can be displayed either on a List or Grid View.









On either display view style, clicking on a workbook title or thumbnail displays the workbook on the *Open Workbook in View Mode*. For more information on how to analyze interactive dashboards, refer to the <u>Client User Guide</u>.

Sorting Workbooks

Sorting workbooks can be done by Name, Last Viewed/Last Published, or Last Viewed by Me.

Steps:

On the Folders and Workbooks Summary layout, either:

□ Click the **Sort By** option on the *Toolbar* of the *Grid View*By default, the sorting is by **Name**.




- Name
- Last Modified
- Last Viewed By Me

Then click the Sort Order.

- Ascending

 Descending
- □ Click on the Name, Last Viewed By Me, or Last Published column header of the List View



Then click the Sort Order.

- Ascending
- Descending

Creating Workbooks


A user with a Designer role can create workbooks using the web authoring tool in Panopticon Real Time. This feature is extensively discussed in the <u>Panopticon Web Authoring Guide</u>.

Renaming Workbooks or Folders


A user with an Administrator or Designer role can rename workbooks and folders.

Steps:

1. Right-click on a workbook or folder then select **Rename** on the context menu.



The Rename Workbook or Rename Folder dialog displays.




2. Enter a new name then click

Uploading Workbooks


Users with an Administrator role can upload workbooks to the currently selected folder in the Workbooks page.

Steps:

1. On the Workbooks page, click on a folder or a personal folder and select Upload Workbook.




The Upload Workbook dialog displays.




- 2. To upload a workbook, you can either:
 - Drag it from your desktop and drop on the dialog, or
 - Click **Choose Workbook** and select one on the *Open* dialog that displays.

The name of the workbook is displayed on the uploaded workbook area and in the *Name* box.



- 3. You can opt to rename the workbook.
- 4. To replace an existing workbook, check the **Replace existing workbook** box.
- 5. Click Upload

You will be notified once the workbook is uploaded.



The workbook is added and displayed.

NOTE

- An error message is displayed if the data source schema of the uploaded workbook has not been updated or missing.
- The uploaded workbook will not include the data source. However, if Panopticon Real Time can reach the same folder of the data source, or the workbook has been designed in the same machine, then the data can be viewed.


Viewing Workbook History and Republishing

Aside from opening workbooks, a user with either an Administrator or Designer role can also perform the following:


- View the change history of workbooks
- Republish an archived workbook to the recent version of Panopticon Real Time
- Rename an archived workbook

Steps:

1. On the Workbooks page, right-click on a workbook or click More Actions and select History in the context menu.




The *History of Workbook <Name>* dialog is displayed with the current version of the workbook indicated.




Sort the archival list either through the *Date Modified* or *Modified By* by clicking on the or button.

Also, move to the other pages of the list by clicking on a page or clicking the or button

- 2. You may opt to rename an archived workbook by entering a new one in the New Name box.
- 3. Click on an archived workbook in the list.








4. Click Yes

A confirmation message displays.

The earlier version of the workbook was successfully republished.

5. Click OK

The republished workbook version is added in the history list.




Moving Workbooks


Users with Administrator or Designer role are allowed to move a workbook to another folder or subfolder they have permission to.

Steps:


- 1. On the *List* or *Grid* view, select one or several workbooks then:
 - Right-click or click **More Actions** and select **Move** in the context menu, or




The Move Workbook dialog displays with the folder or subfolders the user is allowed to move the workbook.



2. Select the folder or subfolder.



 Select the Include linked data tables checkbox so the associated data tables linked inside the workbook will be included when moving.



4. Click Move


The workbook is moved and displayed on the selected folder.

Copying Workbooks


Users with Administrator or Designer role are allowed to copy a workbook to another folder or subfolder they have permission to.

Steps:


- 1. On the *List* or *Grid* view, select one or several workbooks then:
 - Right-click or click **More Actions** and select **Copy** in the context menu, or
 - Click the Copy icon on the toolbar.



The Copy Workbook dialog displays with the folder or subfolders the user is allowed to copy the workbook to.



2. Select the folder or subfolder.



3. Select the **Include linked data tables** checkbox so the associated data tables linked inside the workbooks will be included when copying.

NOTE The Include linked data tables option is available for users with WRITE permissions to the data table.

4. Click Copy


The workbook is copied and displayed on the selected folder.

Sharing Workbooks

You can generate a shareable link of a workbook.

Steps:

1. Right-click on a workbook or click **More Actions** and select **Share** in the context menu.




The Share Workbook dialog displays.



- 2. Click **Copy Shared Link** to copy the generated workbook link that can be shared with other users.
- 3. Click OK

The workbook displays a **Shared Link** icon.



You can click the **Shared Link** icon to copy the link.

- 4. To stop sharing the workbook, right-click on the shared workbook and select **Share** in the context menu. The *Share Workbook* displays.
- 5. Click Stop Sharing

PARAMETER VALUE PASSING INTO THE WEB CLIENT

The Web client uses JSON URL query string to pass parameters.

For example:

/params/{"param1":"value1", "param2":"value2"}

Again, parameter values must be URL encoded:


http://[host:port]/panopticon/workbook/#/[workbook_name]/[dashboard_name]/par
ams/{"param1":"value1","param2":"value2"}

Where:

- Parameters are passed in JSON format
- Every parameter's name should be enclosed in double quotes (i.e., "")
- /params/ sub-path should be placed in prior to JSON sections with parameters
- Special symbols in the parameter values should be URL-encoded. (Refer to <u>Special Symbols to Pass Parameter Values into the HTML5 Client</u> for more information.)

Here is an example URL with parameters that displays one of the example workbooks:

http://localhost:8080/panopticon/workbook/#/How%20to%20Auto%20Parameterize/Summary/params/%7B%22Region%22:%22Europe%22,%22Industry%22:%22Consumer%20Goods%22%7D



This workbook can also be displayed on the web browser using this URL:

http://localhost:8080/panopticon/workbook/#/How to Auto
Parameterize/Summary/params/{"Region":"Europe","Industry":"Consumer Goods"}

To filter specific values, the array of values can be passed again in a standard JSON format, enclosing the array elements into square brackets:

```
{"Region":["Europe", "North America"]}
```

For example:

http://localhost:8080/panopticon/workbook/#/How to Auto Parameterize/Summary/params/{"Region":["Europe","North America"],"Industry":"Consumer Goods"}

Special Symbols to Pass Parameter Values Into the HTML5 Client

When trying to pass parameters to the new HTML5 Client, you need to use URL-encoded characters.

For example, for {"Type": [Soft/Drinks"]} to work, it should be changed to {"Type": [Soft%252FDrinks"]}

Here is a list of double-encoded values you can use to replace their corresponding character.

Character	Double Encode Value	
"<"	"%253C"	
" <i>J</i> "	"%252F"	
">"	"%253E"	

REPLACING PARAMETER VALUES WITH HTTP HEADERS AND COOKIES

Panopticon Real Time can be configured to replace both the incoming and outgoing parameters with HTTP headers and cookies:

- □ **Incoming Parameters** are parameters sent to Panopticon Real Time when requesting data. These types of parameters are also referred to as **request parameters**.
- Outgoing Parameters are parameters which are returned to the Client when retrieving a workbook. These types of parameters are also referred to as response parameters.

This feature is used for employing the user identifier as a parameter and sending the user identifier as a *Header* and *Cookie*. The Server Administrator can configure these properties so that the incoming parameters employ the user identifier value when requesting data. Consequently, the requested HTTP *Header* and *Cookie* values will be tailored for each user. The Server Administrator can also update these properties so that the outgoing parameters get updated when loading a workbook. For example, if you want the user's identifier to be shown in the workbook as a Title

Replacing the parameter values with Header and Cookie values is achieved by configuring certain properties in the Panopticon.properties file located in the Appdata folder or /etc/panopticon/appdata.

Updating incoming parameters can be achieved by configuring the following properties:

Property	Request parameter mapping		
Attribute	request.cookie.parameters.mapping.required		
Description	The parameters that are required to be updated with certain cookie values. This property will only affect incoming parameters. The operation will fail if configured cookie values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Cookie name.		
Default Value			
Property	Request parameter mapping		
Attribute	request.cookie.parameters.mapping.optional		
Description	The parameters that could be updated with certain cookie values. This property will only affect incoming parameters. The operation will not fail if the cookie values are not present in the request. The parameters will keep their default value instead of the configured cookie value if the cookie is not present. The property should be formatted as follows: Parameter name (Value delimiter) Cookie name.		
Default Value			
Property	Request parameter mapping		
Attribute	request.cookie.parameters.mapping.entry.delimiter		
Description	The delimiter that separates the configuration entries. This property will only affect incoming parameters.		
Default Value	, (Comma)		
Property	Request parameter mapping		

Attribute	request.cookie.parameters.mapping.value.delimiter
Description	The delimiter that separates the parameter name and the cookie name. This property will only affect incoming parameters.
Default Value	: (Colon)
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.required
Description	The parameters that are required to be updated with certain header values. This property will only affect incoming parameters. The operation will fail if a configured header values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.optional
Description	The parameters that could be updated with certain header values. This property will only affect incoming parameters. The operation will not fail if the header values are not present in the request. The parameters will keep their default value instead of the configured header value if the header is not present. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.entry.delimiter
Description	The delimiter that separates the configuration entries. This property will only affect incoming parameters.
Default Value	, (Comma)
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.value.delimiter
Description	The delimiter that separates the parameter name and the header name. This property will only affect incoming parameters.
Default Value	: (Colon)

The following properties can be configured to update outgoing parameters:

Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.required
Description	The parameters that are required to be updated with certain Header values. This property will only affect outgoing parameters. The operation will fail if configured Header values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	

Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.optional
Description	The parameters that could be updated with certain Header values. This property will only affect outgoing parameters. The operation will not fail if the Header values are not present in the request. The parameters will keep their default value instead of the configured Header value if the Header is not present. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.entry.delimiter
Description	The delimiter that separates the configuration entries. This property will only affect outgoing parameters.
Default Value	, (Comma)
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.value.delimiter
Description	The delimiter that separates the parameter name and the Header name. This property will only affect incoming parameters.
Default Value	: (Colon)

Example

This section describes how incoming parameters are replaced with Header values. For example, Panopticon Real Time is required to update parameters **uid** and **uname**.

Parameter Name	Update With Header
uid	userIDHeader
uname	userNameHeader

The request will fail if the required *Headers* are not present in the incoming request.

For the next example, Panopticon Real Time will try to update the parameter **ulocation** with **userLocationHeader** header. The parameter value will only be updated if the Header is available.

In both configurations, comma was used as an entry delimiter and colon as a delimiter between the parameter name and the Header name.

However, for outgoing parameters, the property prefix (request) must be changed to response instead.

Configurations:

```
request.header.parameters.mapping.required=uid:userIdHeader,uname:userNameHeader request.header.parameters.mapping.optional=ulocation:userLocationHeader request.header.parameters.mapping.entry.delimiter=, request.header.parameters.mapping.value.delimiter=:
```

NOTE

Mapping the same parameter in both the header and cookie will throw an exception on initialize.

[10] DATA LIBRARY


The *Data Library* page allows creation and management of reusable data tables outside workbooks. Data tables from the data library can be used by multiple workbooks server wide.

Some important concepts to remember:

- □ Bringing data inside workbooks is done through data tables.
- A data table contains metadata for data source connection settings, data query, schema definition, calculated columns, transforms, etc.
- One data table can use only one data connector to connect to a data source.
- ☐ Two or more data tables can be joined to create a new joined data table.
- Data table permissioning and sharing between users or groups is done similarly like workbooks (i.e., using folder tree).
- □ There are four types of data tables. The first three reside at the Data Library.

Data Table Type	Description
Data Store	Users can opt to store data closer to Panopticon server in an embedded database.
Live	Direct connection to source data.
Joined	Two or more different types of data tables joined together creating a new data table.
Uploaded	Uploaded files through any of the file connectors, that consequently becomes a Data Store, after importing to data store.

The Data Library page is composed of the following sections.



Data Library Page Sections and Descriptions

Section	Description
1	Folders
	List of folders where data tables can be saved, exported, or imported.
2	Folder Context Menu Allows you to: Create a data table and joined data table Assign folder permissions on your workspace
	Import or export data table bundlesCreate, rename, or remove folders
3	Search Data Table Entering text will filter data tables which can include: Those that are available in data store Live data tables Joined data tables Extracts
4	Toolbar Allows you to: Display the data tables list either on List View or Grid View Copy or move data tables to other folders Import data table to data store Clear and import data table to data store Delete data tables
5	New Legacy Extract Allows accessing data by retrieving only the required results into memory, by querying on demand, pushing aggregation, and filtering tasks to underlying big data repositories, or queryable data extracts.
6	New Joined Data Table Allows you to join data tables created in the data library.
7	New Data Table Allows you to create a data table.
8	Folders List Available folders.
9	List of Data Tables and Data Extracts Data tables and data extracts created in the data library.
10	Data Table Context Menu Allows you to: Export data table bundles Copy or move data tables to other folders Rename or remove data tables

Section	Description
	View details of the data table
	Set the data policy for data tables in the Data Library
	Convert data extract to data table and import into data store

For more information on using this page, see [4] The Data Library Page section in the Web Authoring Guide.

SETTING UP DATA STORE

To be able to use data store, you would need to set the following properties. By default, Panopticon supports MonetDB, so default values correspond to it.

Also. MonetDB JDBC driver is packaged with Panopticon server. For other data store types, refer to <u>JDBC Driver Installation</u> section.

Property	Data Store
Attribute	datastore.connection.schema
Description	Name of the database schema to be used for creating or managing objects inside database.
Default Value	dbo
Property	Data Store
Attribute	datastore.type
Description	Controls which data store connector should be used. Valid values are MonetDB ", MSSQLServer and PostgreSQL .
Default Value	MonetDB
Property	Data Store
Attribute	datastore.connection.jndi
Description	JNDI resource name for the connection e.g., jdbc/MyDB . More details on how to configure JNDI is at <u>JNDI Connection Details</u> section.
Default Value	
Property	Data Store
Attribute	datastore.connection.url
Description	JDBC connection URL for the database e.g., jdbc:monetdb://localhost:49153/PanopticonDataStore This property value is discarded If datastore.connection.jndiproperty is set.
Default Value	
Property	Data Store

Attribute	datastore.connection.driverclassname
Description	Fully qualified Java class name of the JDBC driver used for the connection.
Default Value	org.monetdb.jdbc.MonetDriver
Property	Data Store
Attribute	datastore.connection.username
Description	Username for the connection. Only required when using connection URL.
Default Value	
Property	Data Store
Attribute	datastore.connection.password
Description	Password for the connection. Only required when using connection URL.
Default Value	

CACHING

Pano	opticon Real Time supports five levels of caching:
	Data Store
	Real-time subscription cache
	Data source cache
	Data table cache
	Query result cache
	f which are optional. If caching is specifically not desired, data requests can always be forwarded to the erlying data repository.
subs requ	subscription cache describes the cache used for streaming subscriptions. This cache is used to ensure scriptions are not duplicated by the server, and that instead the server manages duplicate end client subscriptio ests. Subscriptions are started when the server receives a valid client request and can be set to stop when s are no longer watching data from them or be kept alive until the server is stopped.
the u	data caches simply keep corresponding data sources and tables in memory to avoid unnecessary reloads from underlying data repositories. Neither is used for real-time data, but the data source cache helps with real-time is joined to standing data. The cache entries are keyed on:
	The workbook
	The data table
	The data source
	Parameter values

The time-to-live (TTL) for entries is based on the auto refresh period set on the data table.

The query result cache stores the result of a query from an individual visualization, filter, or legend on a dashboard. It is useful if many users are viewing the same dashboard when many identical queries will be sent in parallel to the server. It also caches real-time data for this purpose.


[11] WEBHOOKS

A webhook is a special URL that makes it possible to send a message from other systems into the system that issued the webhook. Webhook URLs should be treated with care and not shared publicly, since anyone with knowledge about the webhook URL will be able to use it.

Collaboration platforms such as Microsoft Teams, Slack and many others all have support for creating incoming webhooks. In Panopticon, outgoing webhooks can be added (based on incoming webhook URLs from other systems) and used as a channel for sending messages about triggered alerts, like how such messages can also be sent by email. Webhooks added to Panopticon are stored in the server folder structure and are subject to the same permissions model as workbooks.

An outgoing webhook in Panopticon can be used as the message channel for multiple different alerts in multiple different workbooks, due to the parameterization of the webhook request body. The exact structure and content that you should create in the request body of a webhook will be specified in the documentation of the system that issued the webhook.

NOTE Do not expect that the example <u>request body</u> shown below, will work as is.




Property	Description
Search Webhooks	Entering text will filter the webhooks.
Toolbar	Allows copying, moving, and removing of webhooks. Also, to display the webhooks list either on <i>List View</i> or <i>Grid View</i> .

Create Webhooks	Allows creating new webhooks.
Webhooks Context Menu	Allows <u>renaming</u> , <u>moving</u> , <u>copying</u> , <u>deleting</u> , and enabling of the <u>trigger</u> of webhooks.


Folders and Webhooks Display View

Webhooks can be displayed either on a List or Grid View.

On the *Toolbar*, click **Grid View** . The folders and webhooks are displayed as thumbnails.




Or click **List View** , the folders and webhooks are displayed in a standard listing.




On either display view style, clicking on a webhooks title or thumbnail displays the Webhooks page.

Searching for Webhooks

On the Webhooks tab, to search for a particular webhook, enter it in the Search Webhooks box.



You can also enter one of more characters into the *Search Webhooks* box then click **Enter**. The suggested list of webhooks that matched the entries will be displayed.



Click on a webhooks to open and display.

To clear the filter, delete the text entry in the Search Webhooks box.

CREATING WEBHOOKS

This section discusses the instructions and guidelines to create webhooks.

Steps:


On the **Webhooks** tab, click on a folder then
The *New Webhook* dialog displays.

 Hew Webhook




2. Enter the name of the webhook then click

The new webhook is displayed on the Webhook page.



If you want to change the name of the webhook, just enter a new one then click \checkmark .

3. Enter or select the following webhook properties:



Timeout	Timeout (in ms) for reading a response from the URL.
Content Type	The content type of the request body. Default is application/json.
Request Body	<pre>The request body to be supplied to the HTTP call. For example: { 'Alert title': '{_alert_title}', 'Alert dashboard URL': '{_alert_dashboard_url}', 'Alert description': '{_alert_description}', 'Alert reason': '{_alert_reason}', 'Triggering items': '{_alert_triggering_items}', 'Timestamp': '{_current_time}', 'Folder': '{_workbook_folder}', 'Workbook': '{_workbook_name}', 'Dashboard': '{_dashboard_name}' }</pre>

NOTE

URL, *Headers*, and *Request Body* fields can be parameterized (i.e., special server parameters, alert parameters, and <u>global parameters</u>).



- 4. Click

to save the new webhook.

5. You may opt to click to trigger the webhook. Any parameter in the request body will be replaced by its value when triggering the webhook request.

For example


```
{_current_time} - 2021-07-01T12:34:56Z
```

6. Click to go back to the Folders and Webhooks list. The new webhook is added on the list.

WEBHOOKS TOOLBAR AND CONTEXT MENU

Moving, copying, and removing webhooks can either be done using:

_



The Webhooks toolbar options include:

Toolbar Option	Description
Sort By / Sort Order	Allows sorting webhooks by Name, Last Modified, or Last Modified By.
<u>Display View</u>	Display webhooks either by List View or Grid View.
Сору	Copy webhooks to another folder or subfolder where the user has permission.
Move	Move webhooks to another folder or subfolder where the user has permission.
Remove	Remove webhooks.

The Context Menu options include:

Toolbar Option	Description
Rename	Rename the webhook.
Move	Move webhooks to another folder or subfolder where the user has permission.
Сору	Copy webhooks to another folder or subfolder where the user has permission.
Remove	Remove webhooks.
Trigger	Trigger the webhook.

Sorting Webhooks


Sorting webhooks can be done by Name, Last Modified, or Last Modified By.

Steps:

On the Webhooks tab, either:

□ Click the **Sort By** option on the *Toolbar* of the *Grid View*.

By default, the sorting is by Name.




- Name
- Last Modified

Then click the Sort Order.



□ Click on the Name, Last Modified, or Last Modified By column header of the List View.




Then click the Sort Order.

- Ascending
- Descending

Renaming a Webhook

Steps:

1. Right-click on a webhook then select **Rename** on the context menu.



The Rename Webhook dialog displays.



Rename


2. Enter a new name then click

Moving Webhooks


Users with an Administrator role are allowed to move webhooks to another folder or subfolder where they have permission.

Steps:

- 1. Select the checkbox of one or several webhooks either on the *Grid View* or *List View*.
- 2. Then select either:
 - Move icon on the toolbar, or
 - Move on the content menu.



The *Move Webhook* dialog displays with the folder or subfolders that the user is allowed to move the webhooks. Select the folder or subfolder.



3. Click Move


The webhooks are moved and displayed on the selected folder.

Copying Webhooks


Users with an Administrator role are allowed to copy webhooks to another folder or subfolder where they have permission.

Steps:

- 1. Select the checkbox of one or several webhooks either on the Grid View or List View.
- 2. Then select either:
 - Copy icon on the toolbar, or
 - Copy on the content menu.



The *Copy Webhook* dialog displays with the folder or subfolders the user is allowed to copy the webhooks to. Select the folder or subfolder.



3. Click Copy


The webhooks are copied and displayed on the selected folder.

Deleting Webhooks


Users with an Administrator role can remove webhooks.

Steps:

- 1. Select the checkbox of one or several webhooks either on the Grid View or List View.
- 2. Then select either:
 - Remove icon on the toolbar, or
 - Remove on the content menu.




A notification message displays.



Triggering Webhooks

To trigger a webhook, right-click on it and select **Trigger** on the context menu.

to remove.



Any parameter in the request body will be replaced by its value when triggering the webhook request.

For example:

3. Click

```
{_current_time} - 2021-07-01T12:34:56Z
```


[12] ALERTING

The Alerts function allows a notification to be sent when the data in a visualization has met the predefined settings.

If alerts are required to be sent via email, Panopticon Real Time must be configured with valid email server information in the Panopticon.properties file located in the AppData folder (e.g., /etc/panopticon/appdata).

See Panopticon Real Time Configurations for Email Send Outs and Alerts for instructions.

Otherwise, when trying to enable an alert, this error will be displayed:



In addition, you can also set the alert.creation.only.by.administrators property to true for only the Administrators to create alerts.

SETTING UP ALERTS

Alerts can be defined against:

- □ Streaming data sources (including CEP Engines and message queues)
- Periodically refreshed data sources (like REST services, files on HTTP URLs, databases, Python or R)

Alert definition can be done by right-clicking on a streaming numeric or text data in a visualization in the Web Client and setting the limits, duration, what will be included, how many and when an email will be sent.


NOTE

The alert criteria will be evaluated across the full series span along the axis, not on the latest value alone, when using an X-Axis or Y-Axis visualization and the domain axis is using any of the following:

- Text column and is set to Axis Data: Series
- Numeric column
- Time column while the data table does not have a Timeseries Transform applied to it


In contrast, the alert criteria will be evaluated data point by data point as new data is received when using any of the following:

- None-series graphs (such as the Treemap and the Scatterplot)
- Axis graphs that use a nominal text axis or a Timeseries Transformed data table




Steps:


1. Open a workbook on the Web client and right-click on a streaming numeric or text data in a visualization. Select *New Alert* on the context menu.



The Alerts dialog displays with the name of the visualization where the alert will be set.



Sample Text Alerting




Sample Numeric Alerting


2. Enter or select the following properties:

Property	Description
Name	Name of the alert.
Description	Description of the alert.
Search	Search for columns.
Criteria	Criteria set of the alert. Can be multiple, in which case all criteria sets are evaluated in parallel, each triggering respective alerts. Additional criteria sets can be added by clicking . You can also right-click a Criteria tab and select Rename to rename the criteria or select Remove to delete. The Remove option is disabled when only one criteria set is available.
Variable	Available variable columns in the visualization where the alert is set.

Condition	Allows setting the following <i>Limit</i> of all the available numeric variables in the visualization: Upper or Equal To (<=) Lower or Equal To (>=) Upper values (<) Lower values (>) Between – values between the <i>Lower</i> and <i>Upper</i> values For text variables, there are four types of conditions: Equals - The string is equal to another string, e.g., Country=Sweden Not Equals – The string is not equal to another string Wildcard: The string matches a wildcard expression, e.g., Country=Norwa* would match Country=Norway Regex: The string matches a regex expression, e.g., Country=I[a-zA-Z]+a would match Country=India and Country=Indonesia
For the Last	Checks if a value has reached the limit on the set Date/Time unit: second(s) minute(s) hour(s) day(s)
Breakdown	Current breakdown of the visualization.
Parameters	Available parameters in the visualization.
Action Limit	The maximum number of times an alert will be sent on the set Date/Time unit: second(s) minute(s) hour(s) day(s)
Send E-mail	Determines when an alert email will be sent: on enter on leave on enter/leave If unchecked, the notification will only be displayed on the Web client.
Include	Determines whether the image of the visualization or dashboard will be included in the alert email. For the included image of the visualization, check the Use current drill path box to generate a drilled image in the email.
Subject	The subject of the alert's email notifications. See <i>Special Alert Notification Parameters</i> in the Web Authoring Guide for more information.
Body	The content of the alert's email notifications. See Special Alert Notification Parameters in the Web Authoring Guide for more
	information.



3. Select the Active Hours box. The dialog changes to display:



By default, the duration is from 9:00 AM to 5:00 AM on Monday, Tuesday, Wednesday, Thursday, and Friday.

4. To modify the Active Hours, click .

The Clock settings display.



- 5. Select the Hour, Minutes, and AM/PM settings.
- 6. To modify the Active Days, check the boxes of the desired days.
- 7. To apply the active hours in another time zone, select the desired value from the *Show in Timezone* drop-down list box.

Once set, the From and To limits will be applied for that time zone. If not set, the server default time zone will be used.

- 8. Tap the Activated slider to turn it on.
- 9. Click OK

 The new alert is added on the Alerts Definition page.




When creating alerts for grand total, ensure that no breakdown is set.

WORKING WITH ALERTS

Working with alerts can be done either on the *Alerts* page or on the *Alerts* pane of a workbook.

Alerts Page

This page is accessible through the Alerts tab with two sections: Alert Definitions and Alert Events.



Clicking Alert Definitions a displays the list of alerts.


Option	Description
1	Alert Definitions Toolbar Allows you to delete, import, export, deactivate all, or activate all alerts. As an administrator, you are also allowed to share or stop sharing alerts.
2	Show Only Active Alerts Tap the Show only active alerts slider to turn it on. Only the active or enabled alerts are displayed on the Alert Definitions list.
3	Search Alerts Entering text will filter the alerts. You can also enter one or more characters into the Search Alerts box and the suggested list of alerts that matched the entries will be displayed. You can also click of a column to display a multi-select checkbox list. By default, all checkboxes are selected (Select All). Selecting or deselecting items in the list controls the filter.
4	List of Alerts Displays the Title, Workbook, Dashboard, Created By, Creation Time, Enabled, Status, Shared, Times Triggered, Sent Emails, Notifications, and Triggered Webhooks settings of the alerts.

By default, the list of alerts is sorted by Title in ascending order. You can modify the

sorting of the list by clicking the or button of the *Title, Workbook, Dashboard, Created By, Creation Time, Enabled, Status, Shared, Times Triggered, Sent Emails, Notifications, or Triggered Webhooks* columns. The icon beside the column that was used for the sorting will indicate if it was in ascending or descending order.

You can also tap the **Enabled** slider of an alert to turn it on.

Clicking **Alert Events** b displays the details of all triggered events of activated alerts.



Property	Description
Trigger Time	The Date/Time when the alert was triggered.
Title	Title of the alert. Click a Title link to go to the workbook where the alert was triggered.
Description	Description of the alert.
Status	Status of the alert. Can be any of the following: Triggered Resolved Claimed Delegated
Owner	Owner of the alert.

Workbook Name	The workbook name where the alert was set.
Dashboard	The dashboard name where the alert was set.
Alert Events Properties	Displays the workflow changes. Also allows you to: Add a comment Resolve an alert Delegate an alert Claim an alert

You can also do any of the following options:

- \Box Click $\overset{\downarrow}{}$ or $\overset{\uparrow}{}$ of a column title to sort the list.
- □ Click ♥ of a column to display a multi-select checkbox list. By default, all checkboxes are selected (**Select All**). Selecting or deselecting items in the list controls the filter.

Alerts Pane

This pane is accessed by clicking the **Alerts** icon in the workbook or selecting an alert in the pop-up notification. Like the *Alerts* page, there are two screens: **Alert Events** and **Alert Definitions**.



Clicking **Events** a displays the list of alert events.


Option	Description
1	Search Alerts
	Entering text will filter the alert events.
2	Alert Event State
	Allows you to view any of the following alert event states:
	All Open
	My Open
	Shared Open
	All Resolved
	Assigned to me
3	Alert Event Properties
	Displays the following information:
	• Title
	Breakdown details
	Dashboard where the alert is defined

- Date/Time of alert creation
- Workflow changes

Also allows you to:

- Add a comment
- Resolve an alert
- Resolve all open alerts
- Delegate an alert
- Claim an alert

Clicking **Definitions** b displays the list of alerts (**Shared Alerts** or **My Alerts**).



Option	Description
1	Stop Sharing Allows you to stop sharing the alert.
2	Shared Alerts Alerts that are shared by administrators. For each shared alert, the author is displayed. Allows you to:

	Tap the Enable slider to activate the alert
	NOTE: Non-administrators are not allowed to deactivate a running shared alert.
3	My Alerts Toolbar
	Allows you to <u>share</u> , <u>import</u> , <u>export</u> , or delete alerts.
4	My Alerts
	Allows you to:
	Open the alert where you can opt to edit, activate/deactivate, or delete it.
	Activate/deactivate the alert.


Activating or Deactivating All Alerts

Alerts can be activated or deactivated in one click.

To activate all deactivated alerts, click Activate All




. All of the deactivated alerts are activated.



To deactivate all activated alerts, click Deactivate All



. All of the activated alerts are deactivated.






Deleting Alerts

Allows you to delete alert definitions.

Steps:

To delete an alert, select its or all the alerts, select the topmost , then click .
 A notification dialog displays.




2. Click Yes

Importing Alerts

Allows you to import alerts shared by other others.

Steps:

1. On the *Alert Definitions* section of the *Alerts* page or *Alerts* pane, click the **Import Alerts** icon. The *Upload Alert* dialog displays.



- 2. To upload an alert, do one of the following:
 - Drag the file from your desktop and drop on the dialog, or
 - Click Choose alert and then browse and select one on the Open dialog that displays.



A notification displays once the alert is uploaded.



Exporting Alerts

You can download a copy of any of the alerts.


Steps:

- 1. On the Alert Definitions section of the Alerts page or Alerts pane, select the checkbox of the alerts you want to export.
- 2. Click **Export Alerts** icon.


The selected alerts are downloaded.

Viewing and Managing Alerts for Non-Administrator Users

There are three tabs that are available for non-Administrator users:



Click on the Alerts tab to view and manage the available alerts.



See Working with Alerts for more information.

Click the user icon



and click **View Profile**. Then enter the email of the user or group who will receive the alert.

User Profile

Email Address	
mvillanueva@altair.com	
Update Email Address	

Click Update Email Address.

SAMPLE EMAIL ALERTS

An alert is generated when the alert set state changes from **Off** to **On** and recorded in the alert history.

An alert is only issued by email if the alert has not already been sent in the last 'n' minutes as defined in the *Alerts* dialog.

When an alert is issued, an email is sent to the defined email address.


The email includes:

- □ Link to the workbook or dashboard
- Condition and limit value
- □ Breakdown
- Name of the visualization where the alert was set
- PNG image of the visualization or dashboard

Dashboard: http://localhost:8080/panopticon/workbook/#/ecs kx/Visual

Condition: Sum(fills) >= 10.0


The alert was triggered by the following items: algotype:Opportunistic, algoname:Liquidity Driven, sym:O12989, ordername:SIX-NOVN SELL 797k




SAMPLE WEB CLIENT ALERTS

When an alert is triggered, aside from the email notifications, a visual indication or pop-up in active Web clients will draw attention to the alerting visualization or dashboard.

In the example below, alerts initially display highlighted in blue:



The blue highlight eventually fades away.




The pop-up stays on screen until it is closed by clicking the button.

You can open an alert either by:

- Clicking the Alert icon
- Clicking an alert on the pop-up

The item in the workbook that triggered the alert is highlighted.




You can now add comments, resolve, delegate, or claim the alert.

Adding Comments to an Alert


You can add comments to **Open** alerts that you own or are assigned to you.

Steps:

- 1. You can either:
 - Open a workbook and click the Alerts icon to display the Alerts pane




Click an alert on the Alerts Events section of the Alerts tab



2. Click Comment of an alert.


The Comment dialog displays.




OK

3. Enter the comment then click

The comment is added to the alert.



4. Click ** to expand the alert and view all the workflow changes.



5. Add more comments if required.


Resolving an Alert

You can resolve **Open** alerts that you own or are assigned to you.

Steps:

- 1. You can either:
 - Open a workbook and click the Alerts icon to display the Alerts pane. Then select an alert.
 - Click an alert on the Alerts Events section of the Alerts tab.
- 2. Click Resolve

A notification dialog displays.



- 3. Enter the Sleep time to snooze the alert notification.
- 4. Click Yes

Resolving All Open Alerts

You can resolve or close all open events.

Steps:

- 1. Open a workbook and click the **Alerts** \bigcap icon to display the *Alerts* pane.
- Under the alert events, click
 A notification displays.



3. Click Yes

Delegating an Alert

Administrators are allowed to delegate alerts to other users.

Steps:

- 1. You can either:
 - Open a workbook and click the Alerts icon to display the Alerts pane. Then select an alert.
 - Click an alert on the Alerts Events section of the Alerts tab.
- 2. Click Delegate


The Delegate to User dialog displays.



3. Enter the User Name then click




The workflow changes are updated.



The assigned user (e.g., **designer**) will get a notification and will be able to view the alert.

For example:




Claiming an Alert

Administrators can claim alerts that are not assigned to them.

Steps:


- 1. You can either:
 - Open a workbook and click the **Alerts** icon to display the *Alerts* pane. Then select an alert.
 - Click an alert on the Alerts Events section of the Alerts tab.
- 2. Click Claim

A notification displays.



3. Click Yes

The workflow changes are updated.



You can resolve or leave a comment on the alert.

Sharing Alerts


Administrators can share alerts.

Steps:

1. On the Alert Definitions section of the Alerts page or Alerts pane, select one or more alerts then click Share



A notification displays.



2. Click Yes

The selected personal alerts are now moved to the Shared section.

Stopping the Sharing of Alerts

Administrators can also stop the sharing of alerts.

Steps:

1. On the *Alert Definitions* section of the *Alerts* page or *Alerts* pane, select one or more alerts under Shared Alerts then click **Stop Sharing**.

A notification displays.




2. Click Yes

The selected shared alerts are moved to the My Alerts section.

[13] GLOBAL PARAMETERS

The **Parameters** tab supports adding, modifying, and deleting global parameters that will pull and enter specific data into the different sets that are assigned to workbook folders, as well as user specific folders.

For example:




Parameters Set In	Description
Organization's root folder (i.e., Global)	Inherited by all of the available folders and applied to all workbooks
Public root folder (e.g., Global > Orders)	Inherited by the public root folder's subfolders and applied to all public workbooks.
User's root folder (i.e., Global > ~)	Inherited by the user root folder's subfolders and applied to all private workbooks.

ADDING PARAMETERS


Follow the steps below to add global parameters with an Administrator role.

Steps:

On the **Parameters** tab, click the Add icon of a global folder (root or subfolder).
 A new parameter entry displays.



- 2. Enter a Name for the new parameter.
- 3. Select the *Type*: **Text**, **Numeric**, or **Time**.
- 4. Enter the Default Value.




5. Select the *Encrypted* checkbox to encrypt the value, if required.



6. Click . The new parameter is added in the list.


Global parameters added in the parent/root folder are inherited by the corresponding subfolders.




MODIFYING PARAMETERS


Steps:

On the **Parameters** tab, click the **Edit** icon of a parameter.
 The *Name*, *Value*, and *Encrypted* controls are enabled.



2. Make the necessary changes then click .







DELETING PARAMETERS

Steps:

On the **Parameters** tab, click the **Remove** icon
 of a parameter
 A confirmation message displays.




Refresh Parameters




Searching Parameters

To search for a particular parameter, enter it in the Search box.



You can also enter one of more characters into the *Search* box and the suggested list of parameters that matched the entries will be displayed.




[14] MANAGING WORKBOOK THEMES

Workbook themes are set of configurable settings that affect all colors and fonts of dashboards and visualizations in a workbook. This configuration also includes setting which among the <u>color palettes</u> will be available for the Color variable or shape palettes for the Shape variable in the visualizations. Furthermore, the general colors to be used in visualizations such as axis, background, border, and focus colors can be defined.


Theme files are independent of workbooks and can be uploaded to and downloaded from the server through the administration UI.

On an opened workbook, users can dynamically switch to one of the provided default workbook themes: **Light, Light2023**, **Dark,** or **Dark2023**.





The Themes tab allows management of these workbook themes which are stored in the repository on the server.



NOTE

In the previous versions of Panopticon, all of theme-related settings are part of the workbook style, making it difficult to dynamically switch styles (e.g., colors, fonts etc.)

When a workbook (created using versions before 17.5) is opened, all of the existing styles are extracted then saved as its inline workbook theme.


On the **Themes** tab, the following sections are available:

Property	Description
Search Theme	Entering text will filter the themes.
Toolbar	Allows copying, moving, and removing of themes. Also, to display the themes list either on <u>List View or Grid View</u> .
<u>Create Theme</u>	Allows creating new themes.
Theme Context Menu	Allows <u>uploading</u> , <u>renaming</u> , <u>moving</u> , <u>copying</u> , <u>downloading</u> , and <u>deleting</u> themes.


FOLDERS AND THEMES DISPLAY VIEW

Themes can be displayed either on a List or Grid View.

On the *Toolbar*, click **Grid View** . The folders and themes are displayed as thumbnails.




Or click **List View** , the themes are displayed in a standard listing.




On either display view style, clicking on a themes title or thumbnail displays the *Theme* page.

SEARCHING FOR THEMES

On the *Themes* tab, to search for a particular theme, enter it in the *Search Theme* box.



You can also enter one of more characters into the *Search Theme* box then click **Enter**. The suggested list of themes that matched the entries will be displayed.



Click on a theme to open the settings page.

To clear the filter, delete the text entry in the Search Theme box.

CREATING A NEW THEME

Creating a new theme allows setting the default or custom styles, color palettes, general colors, editor, and shape palettes to be used in workbooks and parts.

Steps:


On the *Themes* page, click
 The *New Theme* dialog displays.



Create

2. Enter the name of the theme then click

The new theme is displayed on the *Theme* page.



If you want to change the name of the theme, just enter a new one then click ...


- 3. When creating a new theme, you may specify the following properties:
 - <u>Default Styles</u> Define the default style settings of the workbook, parts, visualizations, filter box, action part title, legend title, actions, and PDF output.
 - <u>Custom Styles</u> Define the settings of the custom styles.
 - Color Palettes Manage, import, or export Text, Sequential, and Diverging color palettes.
 - General Colors Define or create duplicate general color.
 - Editor Define the editor style settings.
 - <u>Shape Palettes</u> Define the settings of shape palettes and add, upload, download, duplicate, or remove them.
 - <u>Dashboard Templates</u> Update or delete default and new dashboard templates.

Defining the Default Style Settings of a Theme

When you define the default settings of a theme, you specify the colors and fonts of the workbook, visualizations, filter box, action part title, legend title, and action form.

Steps:

1. To define the default styles of the workbook, click **Workbook o**n the **Default Styles** tab. The *Workbook Settings* are displayed.




You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the workbook.
Background	Background color of the workbook.
Primary	Primary color of the workbook.
Secondary	Secondary color of the workbook.
On Primary	Foreground color within the primary color.

1.1. To set the colors, you can do one of the following:

• Click the Color box to display the Color dialog and set the Hex color code, RGB, or HSL value



Enter the Hex color code




• Enter the HTML color name



1.2. Select the Font.



- 1.3. Specify the Font Size.
- 1.4. Specify whether **Bold** and **Italic**.
- 2. To define the default styles of the parts, click **Part** on the *Default Styles* pane. The *Part Settings* are displayed.



You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the parts.
Background	Background color of the parts.
Border	Border color of the parts.

- 2.1. Follow step 1.1 to define the visualization, title, and border colors.
- 2.2. Select the part's Font.
- 2.3. Specify the part's Font Size.
- 2.4. Specify whether Bold and Italic.
- 2.5. Specify the Padding of the parts.
 - 2.5.1. To modify the *Top*, *Right*, *Left*, and *Bottom* padding values, click

The page updates to display the following fields:




- 2.5.2. Set the desired padding values. If the values are not the same, **Mixed** is displayed in the *Padding* field.
- 2.6. Specify the *Border Radius*. When set to **0px**, the border is displayed as a sharp corner. Setting to higher values makes the border more rounded.
- 2.7. Specify the Margin of the parts.

2.7.1. To define the *Top*, *Right*, *Left*, and *Bottom* margin values, click



- 2.7.2. Set the desired margin values. If the values are not the same, **Mixed** is displayed in the *Margin* field.
- 3. To define the default styles of the visualizations, click **Visualization** on the *Default Styles* pane. The *Visualizations Settings* are displayed.



You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the visualizations and title.
Background	Background color of the visualizations and title.
Border	Border color of the visualizations.

- 3.1. Follow step 1.1 to define the visualization, title, and border colors.
- 3.2. Select the visualization and title's Font.
- 3.3. Specify the visualization and title's Font Size.
- 3.4. Specify whether **Bold** and **Italic**.



- 3.5. Specify the Border Size of the visualizations.
- 3.6. Select the visualization title Alignment, Left, Center, or Right.
- 3.7. Specify the Padding of the visualizations.
 - 3.7.1. To modify the *Top*, *Right*, *Left*, and *Bottom* padding values, click


 The page updates to display the following fields:



- 3.7.2. Set the desired padding values. If the values are not the same, Mixed is displayed in the Padding field.
- 3.8. Specify the *Border Radius*. When set to **0px**, the border is displayed as a sharp corner. Setting to higher values makes the border more rounded.
- 3.9. Specify the *Margin* of the visualizations.
 - 3.9.1. To define the Top, Right, Left, and Bottom margin values, click



- 3.9.2. Set the desired margin values. If the values are not the same, **Mixed** is displayed in the *Margin* field.
- 3.10. You can opt to define the settings of the *Title Rows*.



By default, there are three title rows. You can do one of the following:

- Click Remove Style to delete, or
 Click Add Title Row Style to add more title rows and define their settings.
- 4. To define the default styles of the filter box, click **Filter Box** on the *Default Styles* pane. The *Filter Box Settings* are displayed.



You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the filter box.
Background	Background color of the filter box.

- 4.1 Follow step 1.1 to define the colors of the filter box.
- 4.2 Select the filter box title's Font.
- 4.3 Specify the filter box title's Font Size.
- 4.4 Specify whether **Bold** and **Italic**.




- 4.5 Select the filter box title *Alignment*. **Left, Center,** or **Right**.
- 5. To define the default styles of the action part title, click **Action Part Title** on the *Default Styles* pane. The *Action Part Title Settings* are displayed.




- 5.1 Select the action part title's Font.
- 5.2 Specify the action part title's Font Size.
- 5.3 Specify whether **Bold** and **Italic**.

NOTE For the action part title, **Bold** is selected by default.

6. To define the default styles of the legend title, click **Legend Title** on the *Default Styles* pane. The *Legend Title Settings* are displayed.




- 6.1 Select the legend title's Font.
- 6.2 Specify the legend title's Font Size.
- 6.3 Specify whether **Bold** and **Italic**.



7. To define the default styles of the different actions (i.e., Action Form, Action Date Picker, Action Button, Action Dropdown, Action Text Box, Numeric Action Slider), click one and on the *Default Styles* pane to display their corresponding settings.

Most of these actions share the same settings as below:



You may opt to modify the colors of the following properties:


Property	Description
Foreground	Foreground color of the action, button, or slider.
Background	Background color of the action, button, or slider.

- 7.1 Follow step 1.1 to define the colors of the actions.
- 7.2 Select the action and button's Font.
- 7.3 Specify the action and button's Font Size.
- 7.4 Specify whether **Bold** and **Italic**.



- 7.5 Specify the action's border color and size.
- 7.6 Specify the Padding of the actions.
 - 7.6.1 To modify the *Top*, *Right*, *Left*, and *Bottom* padding values, click

The page updates to display the following fields:



- 7.6.2 Set the desired padding values. If the values are not the same, **Mixed** is displayed in the *Padding* field.
- 7.7 Specify the *Border Radius*. When set to **0px**, the border is displayed as a sharp corner. Setting to higher values makes the border more rounded.
- 7.8 Specify the *Margin* of the actions.
 - 7.8.1 To define the *Top, Right, Left*, and *Bottom* margin values, click .



- 7.8.2 Set the desired margin values. If the values are not the same, **Mixed** is displayed in the *Margin* field
- 8. To define the default styles of the PDF's header and footer, click **PDF** on the *Default Styles* pane. The *PDF Settings* are displayed.




- 8.1 Follow step 1.1 to define the header and footer's *Foreground* color.
- 8.2 Specify the header and footer's Font and Font Size.
- 8.3 Specify whether **Bold** or **Italic**.
- 8.4 Specify the header and footer's Alignment.
- 9. Proceed to the **Custom Styles** tab to specify the <u>custom styles</u> of the theme.

Defining the Custom Style Settings of a Theme

Published custom style configuration of a part can be modified in the **Custom Styles** tab and can be applied to other parts.

Steps:

1. Click Custom Styles tab. The available published custom styles and properties are displayed.




- 2. See <u>Define Default Styles</u> to specify the settings depending on the custom style part.
- 3. Proceed to the **Color Palettes** tab to define the <u>color palettes</u> of the theme.

Defining the Color Palettes Settings of a Theme

When you define the settings of the color palettes, you can manage, import, or export Text, Sequential, and Diverging color palettes.


Steps:

1. To select the Single, Sign, Text, Sequential, and Diverging color palettes to use within the workbooks, click the Color Palettes tab.



- 2. Select the checkboxes of the provided color palettes that will be included for each category.
- 3. Click the radio button of the preferred *Default* color palette for each category.
- 4. To upload color palettes, click Import Palettes

 The Upload Color Palette dialog displays.



- 5. To export color palettes, you can either:
 - Click Export All Palettes

 for all color palettes. The ColorPalettes.excp file is exported.
 - Click the Export Palette icon of a color palette. The <ColorPaletteName>.excp file is exported.

You can move the exported file to the desired location.

6. To replace the color palettes, select the Replace Color Palettes checkbox.



A notification displays once the color palettes file is uploaded.

Click Cancel to close the dialog. The uploaded color palette is added in the list.


8. Proceed to the **General Colors** tab to specify the <u>general colors</u> of the theme.

Defining the General Color Settings of a Theme


You can specify new general colors or duplicate or remove them.

Steps:


To set the general colors to be used for visualizations, click the General Colors tab.
 By default, the new General Colors is named GeneralColorsLight.




2. Click **Duplicate** to make a duplicate copy of the new general colors.



- 3. You can enter a new name and click . Set Default is turned off and the Remove icon is now available.
- 4. Tap the **Set Default** slider to turn it on and the **Remove** icon is no longer available.



5. Click any of the color boxes to display the *Color* dialog.



Select or specify the new general colors: AxisColor, BackColor, BorderColor, FocusColor, ForeColor, MajorGridColor, MinorGridColor, MissingColor, SelectionColor. SnapshotColor,ZebraStripeColor.

Or enter the corresponding Hex color code.

6. Repeat steps 2 to 5 to add more general colors.

Once the new theme is saved and selected in the opened workbook, all of the defined *General Colors* will be added as options in the *General Colors* drop-down list of a *Color* variable in a visualization.


- 7. Select any of the general colors and tap the Set Default slider to make it the default.
- 8. Select any of the general colors that is not set as the default and click **Delete** to remove
- 9. Proceed to the **Editor** tab to specify the editor style of the **Dark** theme.

Defining the Editor Style Settings of a Theme

You can define the editor style settings of a dark theme.

Steps:

- 1. To set the Foreground, Background, Primary, On Primary, and Secondary colors for the editor style of the **Dark** theme, click the **Editor** tab.
 - ← StocksTheme




- 2. Click on any of the color boxes to display the *Color* dialog and select or enter the preferred color.
- 3. Proceed to the **Shape Palettes** tab to specify the shape palettes of the theme.

Defining the Shape Palettes of a Theme

When you define the shape palettes of a theme, you specify the settings of shape palettes and add, upload, download, duplicate, or remove them.

Steps:

1. To set the shape palettes that can be used with the workbook theme, click the **Shape Palette** tab.




2. Proceed to the **Dashboard Templates** tab to specify the <u>dashboard templates</u> of the theme.

Defining the Dashboard Templates of a Theme


Default dashboard templates are provided in Panopticon. You can modify the name or delete default and new dashboard templates.

Steps:

To modify the dashboard templates that can be used with the workbook theme, click the Dashboard Templates
tab.




- 2. Click on a dashboard template, then you can either:
 - Modify the Title, or
 - Click to delete.
- 3. Click **Save** to save the new theme.
- 4. Clicking the displays the **Themes** tab page with the new theme added in the list.



THEMES TOOLBAR AND CONTEXT MENU

Moving, copying, and removing themes can either be done using:



The toolbar options include:

Toolbar Option	Description
Sort By / Sort Order	Allows sorting of themes by Name, Last Modified, or Last Modified By.
<u>Display View</u>	Display themes either by List View or Grid View.
Сору	Copy themes to another folder or subfolder where the user has permission.
Move	Move themes to another folder or subfolder where the user has permission.
Remove	Remove themes.

The context menu options include:

Toolbar Option	Description
<u>Upload Theme</u>	Upload theme.
Rename	Rename the theme.
Move	Move themes to another folder or subfolder where the user has permission.
Сору	Copy themes to another folder or subfolder where the user has permission.
Remove	Remove themes.

Sorting Themes


Sorting themes can be done by Name, Last Modified, or Last Modified By.

Steps:

On the Themes tab, either:

□ Click the **Sort By** option on the *Toolbar* of the *Grid View*.

By default, the sorting is by Name.




- Name
- Last Modified

Then click the Sort Order.



□ Click on the Name, Last Modified, or Last Modified By column header of the *List View*.




Then click the Sort Order.

- Ascending
- Descending


Renaming a Theme

Steps

1. Right-click on a theme then select **Rename** on the context menu.



The Rename Theme dialog displays.



2. Enter a new name then click


Moving Themes

Users with a Designer role are allowed to move themes to another folder or subfolder where they have permission.

Steps:

- 1. On the List or Grid view, select one or several themes then:
 - Right-click and select Move on the context menu, or
 - Click the **Move** icon on the toolbar.

The *Move Theme* dialog displays with the folder or subfolders that the user is allowed to move the themes. Select the folder or subfolder.



2. Click Move

The themes are moved and displayed on the selected folder.


Copying Themes

Users with a Designer role are allowed to copy themes to another folder or subfolder where they have permission.

Steps:

- 1. On the *List* or *Grid* view, select one or several themes then:
 - right-click and select Copy on the context menu, or
 - click the Copy icon on the toolbar.

The Copy Theme dialog displays with the folder or subfolders the user is allowed to copy the themes to. Select the folder or subfolder.




2. Click Copy

The themes are copied and displayed on the selected folder.

Downloading Themes

On the List or Grid view, right-click on a theme and selected **Download** on the context menu to download a copy.




You can copy this file to the desired location.

Uploading Themes

Users can upload their own workbook themes and also replace existing ones.

Steps:

1. Click on a folder of subfolder where the user has permission to upload a theme then select **Upload Theme** on the context menu.




The Upload Theme dialog displays.



2. To upload a workbook theme, either:

- Drag the file from your desktop and drop on the dialog, or
- Click Choose theme to upload and then browse and select one on the Open dialog that displays

The name of the workbook theme is displayed on the uploaded workbook palette area and in the *Name* box.




You can opt to rename the uploaded workbook theme.

3. To replace the workbook theme, check the *Replace Theme* box.



A notification displays once the file is uploaded.




The uploaded theme is added in the *Theme* list.

Deleting Themes

The default themes (Dark, Dark2023, Light, and Light2023) cannot be removed.


Steps:

- 1. Right-click on one or two themes then either:
 - Select Remove on the context menu, or




• Click the **Remove** icon on the toolbar.

A notification message displays.




COLOR PALETTES

The <u>single</u>, <u>sign</u>, <u>text</u>, <u>sequential</u>, and <u>diverging</u> color palettes that is used in text or numeric color variables in visualizations can be created, imported, exported, <u>modified</u>, <u>duplicated</u>, or <u>deleted</u> in the **Color Palettes** tab of a *Theme* page.



Sign							+
Include	Name						
✓	Light Orange-Blue	0	1	4		=	
~	Light Orange-Green	0	1	4	i	=	
~	Light Red-Blue	0	1	4	iii	=	
~	Light Red-Green	0	1	4		=	
~	Medium Orange-Blue	0	1	4	Ü	•	
✓	Medium Orange-Green	0	1	4	Ü	•	
~	Medium Red-Blue	0	1	4		=	
~	Medium Red-Green	0	1	4		=	
~	Red-Gray	•	1	4	i	=	
Text							
Include	Name						+
✓	Coffee Bean	0	1	4	m	=	
<u> </u>	Fourteen Colors	0	,	4		=	
<u> </u>	Panopticon BI	0	, A.	4	ŵ	=	
<u> </u>	Seven Light Colors	0	,	4		=	
✓	Seven Standard Colors	0	1	4		=	
✓	Spectral	0	, A.	4	ŵ	=	
~	Sunshine	0	1	4	i	=	
~	Twenty Eight Colors	•		4	i	=	
	Twenty Eight Colors Print	0	A.M.	4		=	
✓	Vintage	0		4	ŵ	=	
Sequentia	l						+
Include	Name						
~	Gray	0		Ф		=	
~	Purple-Orange	0		4		=	
~	White-Blue	O	1	Ф	i	=	
	White-Blue-Print	0	a dell'	4		=	
~	White-Green	0		Ф	iii	=	
~	White-Orange	0		Ф	iii	=	
~	White-Red	0	ø	Ф	iii	=	
	White-Red-Print	0	a Maria	ß	i	=	
~	Yellow-Red	0	, A	Ф		=	



NOTE

Creating, modifying, duplicating, or deleting color palettes can also be done inside a workbook in *Web Authoring*. However, these changes will only be associated with the inline theme of the workbook and will not be reflected in the **Color Palettes** tab of the *Themes* page in Panopticon Real Time.

Importing a Color Palette


Users can upload their own color palettes.

Steps:

1. On the Color Palettes pane, click

Import Palettes

The Upload Color Palette dialog displays.




- 2. To upload a color palette, either:
 - Drag the file from your desktop and drop on the dialog, or
 - Click Choose color palettes file to upload and then browse and select one on the Open dialog that displays

The name of the color palette is displayed on the uploaded color palette area.


- 3. To replace the color palettes, check the *Replace Color Palettes* box.
- 4. Click Upload

A notification displays once the color palettes file is uploaded.



Exporting Color Palette

You can either:



You can move the downloaded file to the desired location.

Creating a New Single Color Palette

These are the single colors that will be shared in a workbook for:

- □ records in Table and Record visualizations for the background, text, or shape
- visual members in Combination visualizations for the background or text

Light and medium single color palettes are provided in Panopticon Real Time, but you can also add new ones.


Steps:

On the Single section, click the Add Palette + icon.
 The New Single Palette dialog displays.



- 2. Enter the Title then click 🗸 .
- 3. Click the Color box to display the Color dialog and set the palette color or enter the Hex color code.
- 4. Click Ok

The new single color palette is added in the list (e.g., **Dark Blue**). Note that it is already included and can be modified, duplicated, and deleted.




Creating a New Sign Color Palette

The Sign color palette is used to signify the positive or negative values in numeric visual members.

Steps:


On the Sign section, click the Add Palette + icon.
 The New Sign Palette dialog displays.



- 2. Enter the Title then click .
- 3. To set the *Positive Color* (default is **Gray**) and the *Negative Color* (default is **Red**), click the **Color** box to display the *Color* dialog and select the palette color or enter the Hex color code.



The new Sign color palette is added to the list (e.g., **Red-Green**). Note that it is already included and can be modified, duplicated, and deleted.




Creating a New Text Color Palette

The configuration pane for the Color variable changes depending on the column data type.


In the Web Authoring, when a text column is added to the *Color* variable, the configuration pane displays the color associated with each categorical item, as specified with a default color palette (e.g., **Twenty Eight Colors**).

Steps:

On the Text section, click the New icon.
 The Next Text Palette dialog displays.



- 2. Enter the *Title* then click .
- 3. Select the *Number of Colors* in the drop-down list. Default is **28** colors. The *Other* list is updated accordingly.
- 3. To set the colors, you can do one of the following:
 - Click the Color box to display the Color dialog and set the Hex color code, RGB, or HSL value



Enter the Hex color code




• Enter the HTML color name



4. Click

The new text color palette is added to the list (e.g., **Sixteen Colors**). Note that it is already included and can be <u>modified</u>, <u>duplicated</u>, and <u>deleted</u>.



Creating a Sequential or Diverging Numeric Color Palette

Panopticon visualizations support two types of Numeric Color Palettes: Sequential and Diverging.

Sequential Color Palettes

Sequential palettes use a two-color gradient between a minimum and a maximum value. Numeric column containing only positive values default to a Sequential Palette using the **White-Blue** color palette.

In this case the range *Mid* point is disabled, and the *Min* and *Max* points are populated with defaults from the data set.


Diverging Color Palettes

Diverging Palettes use a three-color gradient between a minimum, middle and a maximum value. Numeric columns containing both positive and negative values default to the Diverging Palette with the **Red White Blue** color palette selected.

Diverging Palettes use the **Range Midpoint**. The *Min*, *Mid* and *Max* points are populated with defaults from the data set.

To create a new sequential numeric color palette:

On the Sequential section, click the New + icon.
 The New Sequential Palette dialog displays.




- 2. Enter the Title and click .
- 3. Select the *Number of Colors* in the drop-down list. Default is **4** colors.

The number of colors from Min to Max is updated accordingly.

4. Set the Outliers, Min, and Max colors. Refer to step 4 of Creating a New Text Color Palette for more information.




The new sequential numeric color palette is added to the list (e.g., **Green-Red**). Note that it is already included and can be <u>modified</u>, <u>duplicated</u>, and <u>deleted</u>.



To create a new diverging numeric color palette:

On the *Diverging* section, click the **New** icon.
 The *New Diverging Palette* dialog displays.



2. Enter the *Title* and click ...


3. Select the *Number of Colors* in the drop-down list. The default is **7** colors.

The number of colors from Min, Mid, to Max is updated accordingly.

4. Set the *Outliers*, *Min*, *Mid*, and *Max* colors. Refer to step 4 of <u>Creating a New Text Color Palette</u> for more information.



The new diverging numeric color palette is added to the list (e.g., **Yellow-White-Red**). Note that it is already included and can be <u>modified</u>, <u>duplicated</u>, and <u>deleted</u>.



Modifying Color Palettes


Any of the included or checked color palettes can be modified.

NOTE

- For the selected default color palette, only the Number of Colors and assigned colors can be modified.
- Color palettes that are not selected cannot be modified.

Steps:

Click the Edit icon of an included or checked color palette.
 The corresponding dialog box displays.




2. Modify the Title, Number of Colors, and assigned colors.



Creating a Duplicate of a Color Palette

Click the **Duplicate** icon of a color palette. A copy of the color palette is added to the list (e.g., **Seven Light Colors 1**).




You can opt to modify the settings.

Deleting Color Palettes

New or duplicate color palettes can be deleted. Click the **Delete** icon to remove the color palette in the list.

SHAPE PALETTES

Shape palettes that can be used with the workbook theme can be <u>created</u>, <u>uploaded</u>, <u>downloaded</u>, <u>modified</u>, <u>duplicated</u>, rearranged, or <u>deleted</u> on the <u>Shape Palettes</u> page.




Creating a New Shape Palette

Steps:


Click Add Palette + .
 A new shape palette displays (i.e., ShapePalette.0).

← Light




Click ShapePalette.<Number>.

The page changes to allow the definition of the new shape palette.



- 3. Enter the shape palette Title and click 🗹 .
- 4. To make this shape palette the default for the workbook theme, tap the **Default Palette** slider to turn it on.




5. To add the shapes, click +.



You can either:

- Click on a shape
- Click Add SVG
 . Select one or more SVG files in the Open dialog box that displays

The added shapes are displayed.




To delete a shape, click its corresponding **Delete** icon

- 6. Select the Default Shape in the drop-down list.
- 7. Click the **Save**

Uploading a Shape Palette


Users can upload their own shape palettes.

Steps:



- 2. To upload a shape palette, either:
 - Drag the file from your desktop and drop on the dialog, or
 - Click **Choose shape palette file to upload** and then browse and select one on the *Open* dialog that displays.


The name of the shape palette is displayed on the uploaded shape palette area and in the Name box.



You can opt to rename the uploaded shape palette.

3. Click Upload

A notification displays once the file is uploaded.



Click

to close the dialog. The uploaded shape palette is added in the list.

Downloading a Shape Palette

You can download a copy of any of the shape palettes.

Click the **Download** icon of a shape palette.

Modifying Shape Palettes


Any of the shape palettes can be modified.

Steps:

- 1. Click on a shape palette to display its settings.
- 2. You can modify the following properties:
 - Title
 - Default Palette. Tap to enable or disable.
 - Add or delete shapes
 - Default Shape
- 3. Click the **Save** icon to save the changes.

Creating a Duplicate of a Shape Palette

Click the **Duplicate** icon of a shape palette. A copy of the shape palette is added in the list (e.g., **Default Shape Palette 1**).



You can opt to modify the settings.

Rearranging Shape Palettes

The order of the shape palettes can be rearranged.


Steps:

1. Click on a shape palette you want to move.


The **Hand Hover** This icon displays along with the blue marker before or after a shape palette where you can drop the item.

2. Drag and drop the shape palette to the desired position.

← Dark



← Dark





Deleting Shape Palettes

Any shape palette can be deleted except the default. Click the **Delete** icon to remove the shape palette in the list.

[15] PCLI: COMMAND UTILITIES FOR PANOPTICON REAL TIME

Panopticon Real Time is supplied with a command line utility PCLI.

This supports the following:

clearcache	Clears the cache on a Panopticon Real Time.
plugins	Troubleshoot the plugins that this program utilizes.
publish	Publishes a workbook to a <u>server</u> or <u>folder</u> .
version	Prints program (and optionally server) version and exits.
help	Use 'help <command/> ' to get help on a specific command.
<u>upgrade</u>	Upgrades specified workbook to the newest version.
schemify	Updates workbook data tables with missing schema information.
exportdatasource	Export workbook data sources.
convertpermissions	Converts old permission files to the new format.
migratedatabasetojdbc	Migrates all usages of the Database connector to JDBC Legacy connector in the given workbook/directory of workbooks.
mockdata	Updates workbook data tables with mock data based on the stored schema.
encrypt	Allows encryption of either a single text or an entire .properties file.
decrypt	Allows decryption of either a single text input or an encrypted .properties file.

Summary help is displayed through: [pcli-folder]>bin/pcli help

More detailed help is displayed through: [pcli-folder]>bin/pcli help [command]

Clearcache

Clears the cache in Panopticon Real Time.

Option	Description
-w,workbook	Workbook name. Syntax example: bin/pcli clearcache -w "workbook" -u "http://username:password@host:port/app_name/"
-d,datatable	Datatable name. Syntax example: bin/pcli clearcache -w "workbook" -d "datatable" -u "http://username:password@host:port /app_name/"
-u,url	<pre>URL to Panopticon Real Time, syntax: bin/pcli clearcache -u http://username:password@host:port/app_name/.</pre>

Command example: bin/pcli clearcache -w "How To Actions" -d

Plugins

Troubleshoot the plugins that this program utilizes.

Option	Description
-v,verbose	Print all information normally traced by the plugin manager.

Publish

You can either publish a workbook to a Panopticon Real Time or to a specific folder.

Publishing a Workbook to Panopticon Real Time

Publishes a workbook to Panopticon Real Time.

Option	Description
-f,force	Overwrite existing workbook on server.
	<pre>Syntax example: bin/pcli publish -w "workbook" -d -u "http://username:password@host:port/app_name/" - n "name" -f</pre>

[&]quot;StocksTimeSeriesFilteredTimeParameters" -u

[&]quot;http://username:password123@localhost:8080/panopticon"

-w,workbook	The workbook file to publish. Syntax example: bin/pcli publish -w "workbook" -u "http://username:password@host:port/app_name/"
-d,dataFiles	Find and upload data files used by workbook.
-u,url	<pre>URL to Panopticon Real Time, syntax: bin/pcli publish -w "workbook" -d -u "http://username:password@host:port/app_name/"</pre>
-n,name	Publish workbook with a different name. Syntax example: bin/pcli publish -w "workbook" -d -u "http://username:password@host:port/app_name/" - n "name"
local	Publishes workbook by file copy, instead of HTTP, for use when server exists on the local system. Specifies target file location path including file name. If the server is running, the application pool must be recycled after publication.
-cp	<pre>Java classpath. Syntax example: \bin/pcli publish -w "workbook" -u "http://username:password@host:port/app_name/"'</pre>

Command example: bin/pcli publish -w "How To Actions.exw" -d -u
"http://username:password123@localhost:8080/panopticon" -n "Published by
pcli" -f

Publishing a Workbook to a Folder

Publishes a workbook to a specific folder.

Option	Description
-w,workbook	The workbook file to publish. Syntax example: bin/pcli publish -w "workbook" -u "http://username:password@host:port/app_name/"
-u,url	URL to Panopticon Real Time, syntax: bin/pcli publish -w "workbook" -d -u "http://username:password@host:port/app_name/" NOTE: The username in the -u command must have permission to the folder. Just being in the list of Administrators is not enough.
-n,name	Publish workbook to a folder on the server with a different name. Syntax example: bin/pcli publish -w "workbook" -d -u "http://username:password@host:port/app_name/" -n "folder\name"
-d,dataFiles	Find and upload data files used by workbook.

Command example: bin/pcli publish -w "E:\Temp\How to Actons.exw" -u
"http://username:password123@localhost:8080/panopticon" -n "test\How to
Actions.exw"

Publishing a Workbook Folder to Panopticon Real Time

Publishes a workbook folder to Panopticon Real Time.

Option	Description
-tf,targetFolder	The target folder to which workbooks will be published. Use -r to publish all workbooks to the ROOT folder. This is only applicable with -wf
	<pre>Syntax example: bin/pcli publish -u "http://username:password@host:port/app_name/" - wf "folder containing workbooks"-tf "server folder name" -r</pre>
-r,root	Publish workbooks to the ROOT folder. This is only applicable with -wf Syntax example: bin/pcli publish -u "http://username:password@host:port/app name/" - wf "folder containing workbooks"-tf "server folder name" -r "default or root folder"
-u,url	<pre>URL to Panopticon Real Time, syntax: bin/pcli publish -w "workbook" -u "http://username:password@host:port/app_name/"</pre>
-wf,workbookFolder	The workbook folder from which workbooks will be picked to publish. Use -w to publish single workbook. Syntax example: bin/pcli publish -u "http://username:password@host:port/app_name/" - wf "folder containing workbooks"-tf "server folder name" -r

Command example: bin/pcli publish

Version

Prints program (and optionally server) version and exits.

Option	Description
-u,url	<pre>URL to Panopticon Real Time, syntax: bin/pcli version -u "http://username:password@host:port/app_name/"</pre>

 $\begin{tabular}{ll} \textbf{Command example:} & \texttt{bin/pcli version -u} \\ \end{tabular}$

[&]quot;http://username:password123@localhost:8080/panopticon" -wf

[&]quot;C:\Serverdata\Data" -tf "C:\Streamsdata\Data" -r

[&]quot;http://username:password123@localhost:8080/panopticon"

Help

Lists all commands or options for a single command.

Command example: bin/pcli help access

Upgrade

Upgrades specified workbook to the newest version.

Option	Description
-w,workbook	Workbook path to upgrade. Syntax example: bin/pcli upgrade -w workbook.exw
-o,output	Output workbook path. Syntax example: bin/pcli upgrade -w workbook.exw -o workbookl.exw

Schemify

Updates workbook data tables with missing schema information.

Option	Description
dd,data-directory	Data directory path. Syntax example: bin/pcli schemify -wd "workbook directory" -od "output directory" -dd "C:\Users\Public\Documents\Panopticon\Data"
-D	Default parameter. This can be supplied either by using: -dp command to pass the path to Parameters.json which is the default parameter file Syntax example: bin/pcli schemify -w "workbook path" - o "output path" -l "license file path" -dp "default parameters file"
	-D switch to specify parameters Syntax example: bin/pcli schemify -w "workbook path" -o "output path" -l "license file path" -D "parameter=value"
-od,output-directory	Output directory path. Syntax example: bin/pcli schemify -wd "workbook directory" -od

	<pre>"C:\Users\Public\Documents\Panopticon\NewWorkbooks" -dd "data directory"</pre>
-w,workbook	Workbook to schemify.
-I,license-file	License file path. Syntax example: bin/pcli schemify -wd "workbook path" - o "output path" -1 "/etc/panopticon/appdata/PanopticonLicense.xml"
-wd,workbook-directory	Directory of the workbooks to schemify.
-o,output	Output path.

Exportdatasource

Export workbook data source.

Option	Description
-dd,data-directory	Data directory path.
-od,output-directory	Output directory path.
-w,workbook	Export data sources of workbook.
-l,license-file	License file path.
-wd,workbook-directory	Directory of workbooks.

```
Command example: bin/pcli exportdatasource -1 "E:\projects\Dashboards
.NET\PanopticonLicense.xml" -w "E:\workbooks\exportdb.exw" -dd
"E:\Serverdata\export" -od "E:\Streamsdata\export" -wd "E:\workbooks"
```

Convertpermissions

Takes an old Workbooks folder and scans it for GroupAccessPermissions.xml files, collects them, and outputs a single file that can then be consumed by the server.

Option	Description
-wf, - workbookFolder	Path to old Workbooks folder, defaults to the current folder.
-o, - outputFile	Path to file where the result will be output. Default is stdout .
-wa, - writersAdmin	If users that had write permission on the old server should additionally get admin permission on the new server, defaults to not. The old server only had read and write , the new one has read , write , and admin .
-tf, - targetFolder	Path to subfolder on target server where you intend to import the workbooks, if not the root folder.

NOTE

Special treatment of empty input folders:

If a workbook folder did not have a

GroupAccessPermissions.xml file, the old server would treat it as if the "Everyone" group had both read and write access to it. This is made explicit in the PCLI verb, which adds this permission to the output.

For example:

pcli convertpermissions -wf
/appdata17/Workbooks/ -o perms.json -wa -tf
/migrated/

This creates perms.json which can then be used to restore the permissions from the old server on the new server if you import the old workbooks into the "migrated" workbook folder.

• See also the <u>Panopticon.properties</u> parameter repository.startup.apply.permissions.path.

MigrateDatabaseToJDBC

Migrates all usages of the Database connector to JDBC Legacy connector to enable editing in the Web Client.

Option	Description
-w, - workbook	Full path of workbook to migrate.
-o,output	Output path. Can be used together with the '-w' option, when a new name to migrated workbook is needed. Output directory should exist.
-od,output-directory	Output directory path. Output directory should exist.
-wd,workbook-directory	Directory of workbooks to upgrade.

Command example: bin/pcli migratedatabasetojdbc -w "E:\ \Workbooks\Database.exw"
-o "E:\MigratedWorkbooks\JDBC.exw"

Mockdata

Updates workbook data tables with mock data based on the stored schema.

Option	Description
-w, - workbook	Workbook to mock the data table data.
-o,output	Output path.

Command example: bin/pcli mockdata -w "z Custom Index - v4 (2).exw" -o MockData.exw Workbooks\z Custom Index - v4: saved updated workbook to MockData.exw

Encrypt

Allows encryption of either a single text or an entire .properties file.

You can optionally move sensitive properties like passwords and URLs from the file Panopticon.properties, where they are stored in clear text, into a file named Secret.properties in the same directory. The Secret.properties file stores values encrypted, and the encryption is achieved by using PCLI and the Encrypt command. A property can only be defined in one of these properties' files at a time. By using the --filter or -f argument, you can match several properties that should have their values encrypted, by regular expression matching, such as for example ".*password" to match any property name ending with the text "password".

Option	Description
-t,text	Text to encrypt.
-p,properties	Input Panopticon.properties file.
-o,output	Output property file.
-f,filter	Property filter regex.

Command examples:

properties file

bin/pcli encrypt -p /etc/panopticon/appdata/Panopticon.properties -o
Define.properties -f .*password

text string

bin/pcli encrypt -t passwordName

Decrypt

Allows decryption of either a single text input or an encrypted .properties file.

Option	Description
-t,text	Text to encrypt.
-p,properties	Input Panopticon.properties file.

Command examples:

properties file

bin/pcli decrypt -p /etc/panopticon/appdata/Define.properties

■ Text string

bin/pcli decrypt -t a7DUF0EONaFBAqNI2W4NoA==

[16] REST INTERFACE

DISCLAIMER

As part of the deprecation of Desktop Designer and related legacy visualization- and data pipelines, we have unfortunately had to retire a set of previously documented REST service endpoints. The endpoints below will no longer be available in the product:

- GET media/image/dashboard
- GET media/image/dashboard/part

All Panopticon APIs should be considered proprietary, internal and subject to change. Going forward, all REST endpoints will be classified into private and publicly supported APIs. Please let us know if your implementation relies on REST API, to ensure that the functionality is made available in future public API

API

Panopticon Real Time exposes services through a REST API. You can use this for scripting and automation, and other tasks like reviewing query statistics and monitoring performance.

NOTE

- You can use PCLI for some common tasks like uploading a workbook and example workbooks to view server performance too.
- For options on how to authenticate against the REST API, see <u>REST and Authentication</u>.

There are two API groups: the **public API**, which is being built out starting in version 2022.1, and the **legacy API**. Going forward, new services will only be added to the public API, and old services may migrate there. Other than that, the main differences are:

The public API	The legacy API
Is officially supported by Altair	Is "unsupported" in the sense that we cannot guarantee that an endpoint will stay unchanged or even remain between releases
Will evolve predictably in the future	
Is designed specifically for REST	Was designed when the server had both REST and SOAP APIs, so is a bit cumbersome from a REST perspective
Has endpoints that begin with /api, e.g., http://localhost:8080/panopticon/api/user/data/profile	Has endpoints that begin with /server/rest

- Has documentation in OpenAPI 3 (see https://openapis.org) at /v3/api-docs/public, e.g., http://localhost:8080/panopticon/v3/api-docs/public
- Has a Swagger UI (see https://swagger.io/tools/swaggerui/) at /swagger-ui.html, e.g.,
 http://localhost:8080/panopticon/swagger-ui.html
- Has a Swagger UI at /swaggerui.html, but you need to select the legacy definition in the top bar

NOTE

The API documentation endpoints and Swagger UI are disabled by default. You need to set ${\tt documentation.enabled=true}$ in

<u>Panopticon.properties</u> (and restart the server) to use them. The REST endpoints and services themselves are always enabled. You should never enable the documentation on a production server.

EXPORT DATA

CSV

Panopticon Real Time provides the functionality to export data from a visualization to a CSV file.

Use the following URL to download the CSV file from the Server:

□ URL: http://[server]/[path]/server/rest/media/data/dashboard/part

Each URL has the following properties:

- Mandatory arguments
 - Workbook Workbook name without an extension.
 - Dashboard Dashboard name in the workbook.
 - Part The visualization part ID

The following examples show how to export the data of a visualization from a local server. For these examples, we have used the example workbook **How To Actions**.

- Export data as a CSV file
 - **Syntax**: http://[server]/[path]/server/rest/media/data/dashboard/part?workbook={Workbook name}&dashboard={Dashboard name}&part={Visualization part id}
 - Example

http://localhost:8080/panopticon/server/rest/media/data/dashboard/part?workbook=How+To+Actions&dashboard=Data+Entry&part=visualization.Treemap1

Dashboard Parameters

The CSV file can be generated based on the workbook data table parameters. The parameter and its values can be specified to determine the context of the exported data.

Syntax:

http://[server]/[path]/server/rest/media/data/dashboard/part?workbook={Workbo
ok name}&dashboard={Dashboard name}&part={Visualization part
id}&{dashboardParameterName1=value1}&{dashboardParameterName2=value2}

Adding Region=Europe and Industry=Financials parameters

Example:

http://localhost:8080/panopticon/server/rest/media/data/dashboard/part?workbook=How+To+Actions&dashboard=Scatter+of+Filtered+Universe&part=visualization.ScatterPlot1&Region=Europe&Industry=Financials

Adding Region=Asia Pacific, or Region=Europe and Industry= Financials parameters produces a CSV file that is focused on Asia Pacific & European Financials. In this case the Region parameter is repeated for each of the supplied regions.

Example:

http://localhost:8080/panopticon/server/rest/media/data/dashboard/part?workbook=How+To+Actions&dashboard=Scatter+of+Filtered+Universe&part=visualization.ScatterPlot1&Region=Asia+Pacific&Region=Europe&Industry=Financials

PDF

Panopticon Real Time provides the functionality to generate and download PDFs. Use the following URL to download PDFs from the server:

URL: http://[server]/panopticon/server/rest/media/pdf

The URL can be accessed through scheduled batch tasks to retrieve and process generated PDFs. (e.g., email to predefined mailing list).

Each URL has the following properties:

- Mandatory arguments
 - Workbook Workbook name without an extension.
- Optional arguments
 - Dashboard Dashboard name in the workbook.
 - **HideScrollbars** Show/Hide the visualization scrollbar in the PDF. Possible values are true/false. The default value is true.
 - EnablePagination Enable pagination in the PDF. Possible values are true/false. The default value is true.

The following examples show how to export a PDF from a local server. For these examples, we have used the example workbook **How To Actions**.

- Generate PDF report of the entire workbook
 - Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Workbook name}
 - Example: http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Actions
- Generate PDF report of the entire workbook in a folder
 - Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Folder name%5CWorkbook name}
 - Example:

http://localhost:8080/panopticon/server/rest/media/pdf?workbook=my+folder%5CHow+To+Actions

NOTE

When the workbook name specifies any folder or subfolders, the path delimiter must be backslash (URL-encoded as %5C) and not forward slash (URL-encoded as %2F).

- ☐ Generate PDF report of a single dashboard in the workbook
 - Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Workbook name}&dashboard={Dashboard name}
 - Example:

http://localhost: 8080/panopticon/server/rest/media/pdf?workbook=How+To+Actions&dashboard=How+Actions&dashboard=How+Actions&dashboard=How+Actions&dashboard=How+Actions&dashboard=How+Actions&dashboard=How+Actions&dashboard=How+Actions&dashboard=How+Actions&dashboard=How+Actions&dashboard=How+Ac

Example (Multiple dashboards): http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Actions&dashboard=How+To+Actions&dashboard=Data+Entry

- Hide scrollbars from visualizations in the PDF
 - Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Workbook name}&hideScrollbars={true/false}
 - Example:

http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Actions&hideScrollbars=true

- Enable or disable pagination of visualizations with vertical scrollbars in the PDF report
 - Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Workbook name}&enablePagination={true/false}
 - Example:

http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Actions&enablePagination=true

Dashboard Parameters

The PDF report can be generated based on the workbook data table parameters. The parameter and its values can be specified to determine the context of the generated PDF report.

Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Workbook
name}&{dashboardParameterName1=value1}&{dashboardParameterName2=value2}

Adding Region=Europe and Industry=Financials parameters

Example

http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Actions&dashboard=Scatter+of+Filtered+Universe&Region=Europe&Industry=Financials

Adding Region=Asia Pacific, or Region=Europe and Industry= Financials parameters produces an output PDF that is focused on Asia Pacific & European Financials. In this case the Region parameter is repeated for each of the supplied regions.

Example:

http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Action s&dashboard=Scatter+of+Filtered+Universe&Region=Asia+Pacific&Region=Europe&In dustry=Financials

Excel Workbook

Panopticon Real Time provides the functionality to export a Panopticon workbook as an Excel workbook. All of the dashboards in the Panopticon workbook will be inserted into their own corresponding Excel sheet. In addition, all of the visualizations in the dashboard will be exported as a PNG image and inserted into an Excel sheet.

The images will be laid out as visualizations on the dashboard. However, the table visualizations will not be exported as images. The visualization tables will instead be exported as Excel tables. The Excel table will always be laid out under all of the exported visualization images.

Please note that only one table will be exported for each dashboard.

Use the following URL to download the Excel workbook from Panopticon Real Time:

URL: http://[server]/[path]/server/rest/media/excel

Each URL has the following properties:

- Mandatory arguments
 - Workbook Workbook name without an extension.
- Optional arguments
 - Dashboard Dashboard name(s) in the Panopticon workbook. All of the dashboards will be exported if no
 dashboard names are provided. The dashboard argument can be used multiple times depending on how
 many dashboards should be exported.
 - Width The width of the exported dashboards. The default value is 1024px.
 - **Height** The height of the exported dashboards. The default value is **768px**.
 - Style The Excel table style of an exported table. The default value is TableStyleMedium7.

The following examples show how to export an Excel workbook from a local server. For these examples, we have used the example workbook **How To Actions**.

- Generate and export Excel workbook
 - **Syntax**: http://[server]/[path]/server/rest/media/excel?workbook={Workbook name}
 - **Example**: http://localhost:8080/panopticon/ server/rest/media/excel?workbook=How+To+Actions
- Set dashboards
 - **Syntax**: http://[server]/[path]/server/rest/media/excel?workbook={Workbook name}&dashboard={Dashboard name1}&dashboard= {Dashboard name2}
 - Example

 $\label{local-bound} \mbox{http://localhost:8080/panopticon/server/rest/media/excel?workbook=How+To+Actions&dashboard=Data+Entry&Dashboard=Time+Parameters \mbox{ } \mbox{$

- Set height and width for Dashboard
 - Syntax: http://[server]/[path]/server/rest/media/excel?workbook={Workbook name}&width={value}&height={value}
 - Example:

http://localhost:8080/panopticon/server/rest/media/excel?workbook=How+To+Actions&width=512&height=384

Set Excel table style

- Syntax: http://[server]/[path]/server/rest/media/excel?workbook={Workbook name}&style={Style}
- Example:

http://localhost:8080/panopticon/server/rest/media/excel?workbook=How+To+Actions&style=TableStyleMedium6

Possible Excel Table Styles

- □ TableStyleLight1− TableStyleLight21
- □ TableStyleMedium1 TableStyleMedium28
- □ TableStyleDark1 TableStyleDark11

Dashboard Parameters

The Excel workbook can be generated based on the workbook data table parameters. The parameter and its values can be specified to determine the context of the generated Excel workbook.

Syntax: http://[server]/[path]/server/rest/media/excel?workbook={Workbook
name}&{dashboardParameterNamel=valuel}&{dashboardParameterName2=value2}

Adding Region=Europe and Industry=Financials parameters

Example:

http://localhost:8080/panopticon/server/rest/media/excel?workbook=How+To+Actions&Region=Europe&Industry=Financials

Adding Region=Asia Pacific, or Region=Europe and Industry= Financials parameters produces an Excel workbook that is focused on Asia Pacific & European Financials. In this case the Region parameter is repeated for each of the supplied regions.

Example:

http://localhost:8080/panopticon/server/rest/media/excel?workbook=How+To+Actions&Region=Asia+Pacific&Region=Europe&Industry=Financials

EMAIL DATA

NOTE

To allow the triggering of the email send out via the REST API, Panopticon Real Time must be configured with valid email server information in the Panopticon.properties file located in the AppData folder (e.g., /etc/panopticon/appdata).

See Panopticon Real Time Configurations for Email Send Outs and Alerts for instructions.

PDF

Panopticon Real Time provides the functionality to generate and email PDFs.

This feature works exactly as the URL PDF generation and uses the same URL parameters. The main difference between the two features is that this feature sends the PDF in an email rather than downloading it as a file. Another difference is this feature requires a POST request to the following URL:

http://[server]/[path]/server/rest/media/pdf/email.

Usage

The following properties can be configured:

- □ URL: http://[server]/[path]/server/rest/media/pdf/email
- Method: POST
- Content-Type: application/json
- Request body:
 - **bodyText** The text will appear in the message body. The text can be formatted in HTML. Special characters, such as double quotation marks (") should have a backslash preceding them in order for the Server to regard them as special characters.
 - to One or more email recipients. Comma is used as a delimiter to separate the email recipients.
 - cc One or more email recipients. Comma is used as a delimiter to separate the email recipients.
 - **bcc** One or more email recipients. Comma is used as a delimiter to separate the email recipients.
 - sender The sender's email address. This value will also be used as a username.
 - senderpassword The password to the sender's email account.
 - subject the subject of the email.

Example

For example, an On-Demand PDF will be emailed based on the following information:

Property	Description
Workbook	How to Actions
Dashboard Name	Scatter of Filtered Universe
Recipients (To)	to-mail1@mail.com to-mail2@mail.com
Sender	from-mail@mail.com
Password	password
Subject	Altair PDF Generator
Body Message	Hello. This is an auto-generated PDF.

As an example:

Panopticon configuration (Panopticon.properties):

```
email.host=smtp.server.com
email.port=587
email.security.mode=TLS
```

URL:

http://localhost:8080/panopticon/server/rest/media/pdf/email?workbook=How+To+Actions&dashboard=Scatter+of+Filtered+Universe

Body:

```
"bodyText": "<h1>Hello.</h1>This is an auto-generated PDF.",
   "to": "to-maill@mail.com, to-mail2@mail.com",
   "sender": "from-mail@mail.com",
   "senderPassword": "password",
   "subject": "Altair PDF generator"
}
```

Image

Panopticon Real Time provides the functionality to generate and email dashboard images.

This feature is similar with Email PDF discussed above and uses the same URL parameters. However, this feature sends dashboard images as part of the email body and not as a PDF attachment. In addition, it does not support pagination.

In addition, hyperlinks can also be used in email dashboard images. Hyperlinks can redirect to a workbook and a dashboard in the server.

NOTE

In cases when you <u>schedule the emailing of dashboard images</u> or when you are behind a proxy or load balancer, it is recommended to specify the server address in the Panopticon.properties file.

For example:

server.host=http://www.company.com/dashboards/

The email contains the following Body components:

Body message: The email starts with the provided body message in the request.
Dashboard Title: The title displays before the dashboard image and uses a h2 heading tag
Dashboard image: The image (.png) of the dashboard.

Usage

Ш	URL: http://[server]/[path]/server/rest/media/image/dashboard/email
	Method: POST
	Content-Type: application/json
	Request body:

- **bodyText** The text will appear in the message body. The text can be formatted in HTML. Special characters, such as double quotation marks (") should have a backslash preceding them in order for the Server to regard them as special characters.
- to One or more email recipients. Comma is used as a delimiter to separate the email recipients.
- cc One or more email recipients. Comma is used as a delimiter to separate the email recipients.
- **bcc** One or more email recipients. Comma is used as a delimiter to separate the email recipients.
- sender The sender's email address. This value will also be used as a username.
- senderpassword The password to the sender's email account.
- **subject** The subject of the email.
- **useHyperlink** The property that determines whether the images should be hyperlinks. The hyperlink then opens the dashboard in the Thin Client. Hyperlinks will be used when set to true (default value). The images will be regular images and not a hyperlink when the property is set to **false**.

Example

Property	Value
Workbook	How to Actions
Dashboard Name	Scatter of Filtered Universe
Recipients (To)	to-mail1@mail.com to-mail2@mail.com
Sender	from-mail@mail.com
Password	password
Subject	Altair Image Generator

Body Message	Hello. This email contains dashboard images.
Use hyperlink	true

As an example:

```
Panopticon configuration (panoption.properties):
email.host=smtp.server.com
email.port=587
email.security.mode=TLS
URL:
http://localhost:8080/panopticon/server/rest/media/image/dashboard/email?work
book=How+To+Actions&dashboard=Scatter+of+Filtered+Universe
Body:
{
    "bodyText": "<h1>Hello.</h1>This email contains dashboard
images.",
    "to": "to-mail1@mail.com, to-mail2@mail.com",
    "sender": "from-mail@mail.com",
    "senderPassword": "password",
    "subject": "Altair Image generator",
    "useHyperlink": "true"
}
```

[17] LOGGING/MONITORING

SERVER LOGGING

Log	ing occurs:	
	Within the platform	
	In the underlying web / application server	
	In the underlying OS	
Pan	pticon Real Time logs are written to the Tomcat logs folder.	
The	ogging level can be set from:	
	Error – Only Errors are logged (the Default)	
	Info – Operational logging is enabled including logging of data queries.	
	Finest – All possible debugging logging is enabled.	
	cally, when support issues are raised, the user is requested to change the logging level to INFO , who conally records:	ch
	Data Plugin (Visualization and Data Connector) Initialization	
	Data Cache Initialization	
	Data Subscriptions	
	Data Queries including:	
	Database connection settings	
	Database SQL query	

Data query logging capabilities are specific to each data connector, with the most detailed logging available for the Database and kdb+ connectors.

Panopticon Real Time logging and auditing capabilities include Java JMX counters for usage and load monitoring, and additional logging around secured access to workbooks.

Configuring Server Logs

Panopticon Real Time is preconfigured with recommended logging settings for performance. All of the logging will be directed to a file prefixed by panopticon in the Tomcat logs folder. The Panopticon-specific logging configuration file is located inside the .war file at WEB-INF/classes/logging.properties. This configuration takes precedence over the general Tomcat logging configuration. If the logging is to be configured in Tomcat, the file WEB-INF/classes/logging.properties must be removed from the .war file.

Number of rows & columns retrieved, and response time

Configuring Apache Tomcat Logs¹

A wah application rupping on Apparla Tamort con-

The internal logging for Apache Tomcat uses **JULI**, a packaged renamed fork of <u>Apache Commons Logging</u> that is hard-coded to use the <code>java.util.logging</code> framework. This ensures that Tomcat's internal logging and any web application logging will remain independent, even if a web application uses Apache Commons Logging.

To configure Tomcat to use an alternative logging framework for its internal logging, follow the instructions provided by the alternative logging framework for redirecting logging for applications that use <code>java.util.logging</code>. Keep in mind that the alternative logging framework will need to be capable of working in an environment where different loggers with the same name may exist in different class loaders.

A w	eb application running on Apache Tomcat can.
	Use any logging framework of its choice
	Use system logging API, java.util.logging
	Use the logging API provided by the Java Servlets specification: javax.servlet.ServletContext.log()

The logging frameworks used by different web applications are independent. See <u>class loading</u> for more details. The exception to this rule is <code>java.util.logging</code>. If it is used directly or indirectly by your logging library, then the elements of it will be shared across web applications because it is loaded by the system class loader.

Java Logging API (java.util.logging)

Apache Tomcat has its own implementation of several key elements of <code>java.util.logging</code> API. This implementation is called **JULI**. The key component there is a custom LogManager implementation, that is aware of different web applications running on Tomcat (and their different class loaders). It supports private per-application logging configurations. It is also notified by Tomcat when a web application is unloaded from memory, so that the references to its classes can be cleared, preventing memory leaks.

This <code>java.util.logging</code> implementation is enabled by providing certain system properties when starting Java. The Apache Tomcat startup scripts do this for you, but if you are using different tools to run Tomcat (such as jsvc, or running Tomcat from within an IDE), you should take care of them by yourself.

Servlets Logging APICalls to javax.servlet.ServletContext.log(...) to write log messages are handled by internal Tomcat logging. Such messages are logged to the category named

```
org.apache.catalina.core.ContainerBase.[${engine}].[${host}].[${context}]
```

This logging is performed according to the Tomcat logging configuration. You cannot overwrite it in a web application.

The Servlets logging API predates the <code>java.util.logging</code> API that is now provided by Java. As such, it does not offer you much options. e.g., you cannot control the log levels. It can be noted, though, that in Apache Tomcat implementation the calls to <code>ServletContext.log(String)</code> or <code>GenericServlet.log(String)</code> are logged at the <code>INFO</code> level. The calls to <code>ServletContext.log(String, Throwable)</code> or <code>GenericServlet.log(String, Throwable)</code> are logged at the <code>SEVERE</code> level.

Console

When running Tomcat on unixes, the console output is usually redirected to the file named catalina.out. The name is configurable using an environment variable. Whatever is written to System.err/out will be caught into that file. That may include:

1 1		بطالم مدمنت ما	:	Thus a al	10	uncaudhtEx	:/ \
Lincalioni	AACAUHUUS	Drinted N	v iava iar	na intean	u -rain	uncallantey	CENTION

¹ http://tomcat.apache.org/tomcat-9.0-doc/logging.html

☐ Thread dumps, if you requested them via a system signal

When running as a service on Windows, the console output is also caught and redirected, but the file names are different.

The default logging configuration in Apache Tomcat writes the same messages to the console and to a log file. This is great when using Tomcat for development, but usually is not needed in production.

Old applications that still use System.out or System.err can be tricked by setting swallowOutput attribute on a Context. If the attribute is set to true, the calls to System.out/err during request processing will be intercepted, and their output will be fed to the logging subsystem using the javax.servlet.ServletContext.log(...) calls.

Note, that the **swallowOutput** feature is actually a trick, and it has its limitations. It works only with direct calls to System.out/err, and only during request processing cycle. It may not work in other threads that might be created by the application. It cannot be used to intercept logging frameworks that themselves write to the system streams, as those start early and may obtain a direct reference to the streams before the redirection takes place.

Access Logging

Access logging is a related but different feature, which is implemented as a **Valve**. It uses self-contained logic to write its log files. The essential requirement for access logging is to handle a large continuous stream of data with low overhead, so it only uses Apache Commons Logging for its own debug messages. This implementation approach avoids additional overhead and potentially complex configuration. Please refer to the <u>Valves</u> documentation for more details on its configuration, including the various report formats.

Using java.util.logging (Default)²

The default implementation of <code>java.util.logging</code> provided in the JDK is too limited to be useful. The key limitation is the inability to have per-web application logging, as the configuration is per-VM. As a result, Tomcat will, in the default configuration, replace the default LogManager implementation with a container friendly implementation called <code>JULI</code>, which addresses these shortcomings.

JULI supports the same configuration mechanisms as the standard JDK <code>java.util.logging</code>, using either a programmatic approach, or properties files. The main difference is that <code>per-classloader</code> properties files can be set (which enables easy redeployment friendly webapp configuration), and the properties files support extended constructs which allows more freedom for defining handlers and assigning them to loggers.

JULI is enabled by default, and supports per classloader configuration, in addition to the regular global java.util.logging configuration. This means that logging can be configured at the following layers:

Globall
 CHODAIN

That is usually done in the \${catalina.base}/conf/logging.properties file. The file is specified by the java.util.logging.config.file System property which is set by the startup scripts. If it is not readable or is not configured, the default is to use the \${java.home}/lib/logging.properties file in the JRE.

In the web application

The file will be WEB-INF/classes/logging.properties

The default logging.properties in the JRE specifies a ConsoleHandler that routes logging to System.err. The default conf/logging.properties in Apache Tomcat also adds several FileHandlers that write to files.

² http://tomcat.apache.org/tomcat-9.0-doc/logging.html

A handler's log level threshold is **INFO** by default and can be set using **SEVERE**, **WARNING**, **INFO**, **CONFIG**, **FINE**, **FINER**, **FINEST** or **ALL**. You can also target specific packages to collect logging from and specify a level.

To enable debug logging for part of Tomcat's internals, you should configure both the appropriate logger(s) and the appropriate handler(s) to use the FINEST or ALL level. e.g.:

```
org.apache.catalina.session.level=ALL
java.util.logging.ConsoleHandler.level=ALL
```

When enabling debug logging it is recommended that it is enabled for the narrowest possible scope as debug logging can generate large amounts of information.

The configuration used by JULI is the same as the one supported by plain <code>java.util.logging</code>, but uses a few extensions to allow better flexibility in configuring loggers and handlers. The main differences are:

A prefix may be added to handler names, so that multiple handlers of a single class may be instantiated. A prefix is a String which starts with a digit and ends with '.'. For example, 22foobar . is a valid prefix.
$\textbf{System property replacement is performed for property values which contain $ \{ \texttt{systemPropertyName} \}. \\$
If using a class loader that implements the org.apache.juli.WebappProperties interface (Tomcat's web application class loader does) then property replacement is also performed for \${classloader.webappName}, \${classloader.hostName} and \${classloader.serviceName} which are replaced with the web application name, the host name and the service name respectively.
By default, loggers will not delegate to their parent if they have associated handlers. This may be changed per logger using the loggerName.useParentHandlers property, which accepts a Boolean value.

The root logger can define its set of handlers using the .handlers property.

By default, the log files will be kept on the file system forever. This may be changed per handler using the handlerName.maxDays property. If the specified value for the property is <=0 then the log files will be kept on the file system forever, otherwise they will be kept the specified maximum days.

There are several additional implementation classes, that can be used together with the ones provided by Java. The notable one is org.apache.juli.FileHandler.

org.apache.juli.FileHandler supports buffering of the logs. The buffering is not enabled by default. To configure it, use the bufferSize property of a handler. The value of 0 uses system default buffering (typically an 8K buffer will be used). A value of <0 forces a writer flush upon each log write. A value >0 uses a BufferedOutputStream with the defined value but note that the system default buffering will also be applied.

Example logging.properties file to be placed in \$CATALINA BASE/conf:

```
handlers = 1catalina.org.apache.juli.FileHandler, \
         2localhost.org.apache.juli.FileHandler,
         3manager.org.apache.juli.FileHandler, \
         java.util.logging.ConsoleHandler
.handlers = 1catalina.org.apache.juli.FileHandler, java.util.logging.ConsoleHandler
# Handler specific properties.
# Describes specific configuration info for Handlers.
1catalina.org.apache.juli.FileHandler.level = FINE
lcatalina.org.apache.juli.FileHandler.directory = ${catalina.base}/logs
1catalina.org.apache.juli.FileHandler.prefix = catalina.
2localhost.org.apache.juli.FileHandler.level = FINE
2localhost.org.apache.juli.FileHandler.directory = ${catalina.base}/logs
2localhost.org.apache.juli.FileHandler.prefix = localhost.
3manager.org.apache.juli.FileHandler.level = FINE
3manager.org.apache.juli.FileHandler.directory = ${catalina.base}/logs
3manager.org.apache.juli.FileHandler.prefix = manager.
3manager.org.apache.juli.FileHandler.bufferSize = 16384
java.util.logging.ConsoleHandler.level = FINE
java.util.logging.ConsoleHandler.formatter = java.util.logging.SimpleFormatter
# Facility specific properties.
# Provides extra control for each logger.
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].level = INFO
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].handlers = \
  2localhost.org.apache.juli.FileHandler
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].[/manager].level = INFO
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].[/manager].handlers = \
  3manager.org.apache.juli.FileHandler
# For example, set the org.apache.catalina.util.LifecycleBase logger to log
# each component that extends LifecycleBase changing state:
#org.apache.catalina.util.LifecycleBase.level = FINE
```

Example logging.properties for the servlet-examples web application to be placed in WEB-INF/classes inside the web application:

```
handlers = org.apache.juli.FileHandler, java.util.logging.ConsoleHandler
# Handler specific properties.
# Describes specific configuration info for Handlers.
org.apache.juli.FileHandler.level = FINE
org.apache.juli.FileHandler.directory = ${catalina.base}/logs
org.apache.juli.FileHandler.prefix = ${classloader.webappName}.
java.util.logging.ConsoleHandler.level = FINE
java.util.logging.ConsoleHandler.formatter =
java.util.logging.SimpleFormatter
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].[/manager].leve
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].[/manager].hand
lers = \
   3manager.org.apache.juli.FileHandler
# For example, set the org.apache.catalina.util.LifecycleBase logger to log
# each component that extends LifecycleBase changing state:
#org.apache.catalina.util.LifecycleBase.level = FINE
```

AUDIT LOGGING

Panopticon Real Time can also produce audit logs. All of the audit logging will be directed to a file prefixed 'panopticon-audit' in the Tomcat log folder. The audit logs can be configured just like the regular logs produced by Panopticon Real Time. Refer to Configuring Panopticon Real Time Logs for more information on how to configure logs.

Panopticon Real Time is pre-configured to generate audit logs on an **INFO** level. Most of the messages are logged with **INFO** level. However, there are certain actions that are logged at different levels, such as **FINE**.

The audit logs contain the following information:

Attribute	Description
Timestamp	Timestamp for when the executed action occurred. The format of the timestamp is YYYY-mm-ddTHH: MM: SS (e.g., 2015-12-24T15:30:40).
Log Level	The severity of the log level.
Username	The username of the user that executed the action. The username will be ANONYMOUS if the user is not authenticated.
IP-address	The user's IP address.
Action	Detailed message about the executed action.

Audit logs use comma (,) as a delimiter to separate these values.

DATA LOG ACCESS IN DASHBOARDS

The subscription.data_log.always_on server property has a false default value. When set to true, the data log is always passed from server to client if the user is a Designer or Admin on the server. Previously, the data log would only be passed for workbooks in design mode.

The data log will be passed also when the data request fails. The "Invalid Configuration" message shown in the visualization will show a "Data Log" button, which will display the relevant logs and error message.

NOTE

The actual passing of runtime exception is currently implemented in the Kdb+connector only.

The benefit of running a server with subscription.data.log.always_on=true is that, the data log is more easily accessed and can be viewed both as success and failure. The data log can also be viewed without having **Write** permissions on the folder where the workbook is used, which is helpful when connection failures need to be examined in production environments where you have restrictions on workbook editing.

NOTE

Viewer users are not able to view the Data Log, only Designers and Admins.

SERVER MONITORING

Panopticon Real Time	publishes the	following,	JMX counters:
----------------------	---------------	------------	---------------

- ServerDataRequestCount
- □ ActiveDataRequestCount
- InfoMessageCount
- ErrorMessageCount
- ActiveRealtimeSubscriptionCount
- LoadedWorkbooksCount
- MemoryStoreObjectCount
- ObjectCount

These can be accessed through any JMX monitoring toolset, such as Jconsole from the Java Development Kit (JDK).

As a basic configuration:

- 3. Download and install Java Development Kit (JDK)


 http://www.oracle.com/technetwork/java/javase/downloads/jdk8-downloads2133151.htm
- 4. Add the following parameters to your Tomcat:
 - Dcom.sun.management.jmxremote.port=8855
 - Dcom.sun.management.jmxremote.authenticate=false

- -Dcom.sun.management.jmxremote.ssl=false
- 5. Open Jconsole. The jconsole executable can be found in <code>JDK_HOME/bin</code>, where <code>JDK_HOME</code> is the directory in which the Java Development Kit (JDK) is installed.
- 6. When the connection dialog opens, you are also given the option of connecting to a remote process.
 - Host name: name of the machine on which the Java VM is running.
 - Port number: the JMX agent port number you specified when you started the Java VM (e.g., 8855)

WEB PORTAL INTEGRATION

NOTE Set the documentation.enabled property in Panopticon.properties to true to view the documentation.

Panopticon workbooks can be embedded into existing portals with minimal effort. Open [tomcat]/panopticon/panopticon-api-doc/index.html to view the documentation.



SETTING THE SERVER METRICS PUBLISHER

The server performance metrics can be used to report, monitor, and configure the server's health and limits. The collected metrics may include the following information:

- □ Long polling, WebSocket, and total number of connections
- CPU loading percentage
- Maximum, size, and used Heap Bytes
- Subscription alerts, users, and total

- Number of parallel data loading and live threads
- Average data load time or refresh rate

You can configure the following properties in the $\underline{\texttt{Panopticon.properties}}$ file located in the $\underline{\texttt{AppData}}$ folder or $\underline{\texttt{/etc/panopticon/appdata}}$:

Property	Server Metrics
Attribute	metrics.authorization.level
Description	Specifies the required authorization level to get server metrics. Available values are ANONYMOUS , VIEWER , DESIGNER , ADMINISTRATOR . NOTE: This property is case sensitive.
Default Value	ADMINISTRATOR
Property	Server Metrics
Attribute	metrics.collection.rate
Description	Specifies the rate at which metrics are collected in milliseconds.
Default Value	1000
Property	Server Metrics
Attribute	metrics.file.flush.rate
Description	Specifies how often metrics should be saved to disk in milliseconds. Only used if the metrics.publisher.type is set to FILE.
Default Value	10000
Property	Server Metrics
Attribute	metrics.memory.queue.size
Description	Specifies how many metric entries are stored in memory. When the number of metrics goes above the specified value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY .
Default Value	100
Property	Server Metrics
Attribute	metrics.publisher.configuration
Description	Specifies the id for which metric publisher configuration to use.
Default Value	
Property	Server Metrics
Attribute	metrics.publisher.type
Description	Specifies the current metric publisher that is used. Available values are NONE , MEMORY , FILE , EMAIL , INFLUX_DB , JDBC , KAFKA , KDB , MQTT , REST , TEXT .
Default Value	MEMORY

SETTING THE LOGGING LEVEL

Changes to the logging level can be made by altering the value of logger.level.file in the Panopticon.properties file. The server will not log messages with a lower/finer level than this value. The separate logging configuration still applies to route whatever messages that the server does log. This means that if you have set the file handler's level to **INFO** in the configuration, setting the property to **FINE** has no effect.

The default value of the property is set to **INFO**. At this level, most information needed for troubleshooting is logged, including many data queries, timing, and parameters. With a lower/finer level performance will be affected due to the amount of information logged.

[18] TROUBLESHOOTING

RESOLVING INSTALLATION ISSUES

Issues are investigated and resolved through investigation and controlled reproduction. Several known issues are included in the next section and predominately relate to problematic installations of Panopticon Real Time.

If you experience an unknown issue, send complete details to: dasupport@altair.com

Be sure to send this important information to Altair Support in the event of a problem.

Server Log

Panopticon Real Time log files are located in the [tomcat home] \logs folder.

The level of detail for these log files are configured at the "level" sections of logging.properties file in [tomcat home] \conf folder.

By default, it is set to Error, while the most verbose is Info.

Steps:

1. Edit the value of "level" in the logging.properties file:

From:

org.apache.catalina.core.ContainerBase.[Catalina].[localhost].level = ERROR

To:

org.apache.catalina.core.ContainerBase.[Catalina].[localhost].level = INFO

NOTE

Modifying the level setting will consume more disk space, so make sure to only do this while troubleshooting.

2. Restart Tomcat after making these changes.


NOTE

Refer to **Configuring Server Logs** for more information.

When sending your issue, include your workbook and associated data sources if the issue is specific to a particular workbook.

PIE CHARTS AND SHAPES NOT DISPLAYING CORRECTLY IN CHROME

When Hardware Acceleration is enabled in Chrome, Pie Chart and Shape visualization may not display as expected. For example:



To resolve this issue, follow the steps below to disable Hardware Acceleration in Chrome:

- 1. Open the Chrome web browser.
- 2. You can either:
 - Click to the right of the Address box and select Settings
 - Or enter chrome://settings in the Address box.
- 3. Scroll to the bottom of the page and click Show Advanced Settings...
- 4. Uncheck Use Hardware Acceleration when Available box.

System

- Continue running background apps when Google Chrome is closed
- Use hardware acceleration when available (requires Chrome restart)
- 5. Restart Chrome.

MANAGED ALTAIR UNITS LICENSE SSL ERROR

If you encounter the following issue when using Managed Altair Units license:

 $"SSL_ERROR_SSL$

error:14007086:SSL routines:CONNECT_CR_CERT:certificate verify failed

unable to get local issuer certificate" Detail: SSL/TLS handshake failed

Follow the steps below to resolve this error:

- 1. Make sure you have installed all updates and are using the latest version of the product. The latest version is always available from the Marketplace.
- 2. Work with your IT department to create an exception in your proxy for the traffic going to our servers:
 - https://client.hhwu.altair.com
 - https://auth.hhwu.altair.com
 - https://auth.login.solidthinking.com
 - https://auth.admin.altairone.com
 - https://alas.admin.altairone.com


[19] KNOWN ISSUES

OUT OF MEMORY EXCEPTION

If the data is too big, an out of memory exception may occur. To increase the memory of Panopticon Real Time in Tomcat for Linux, refer to <u>Tomcat Memory Configuration for Linux</u> for more information.

[20] PANOPTICON RESOURCES

Clicking the user profile icon on the top right section of the toolbar displays the other Panopticon online resources that users with an Administrator role can access.




Modified 2 mon

Select the Language on the drop-down list: English or Japanese.

Modified 2 months ago

Logout



Resource	Description
Release Notes	List of new features and fixed issues in the release.
Technical Fact Sheet	Overview of the Panopticon components which consists of: system requirements features supported data connectivity and visualizations custom code data connections, transforms, and ML model scoring filtering and data capabilities
Real Time Reference Guide	Panopticon Real Time documentation for users with an Administrator role which consists of: installation, system requirements, and licensing options supported authentication mechanisms advanced and optional steps or deployments system administration of the server including the logs, subscriptions, caches, scheduled tasks, and logged in users viewing and managing of workbooks and data templates creating and managing of data templates, global parameters, alerts, workbook themes PCLI command utilities REST API examples troubleshooting guide Panopticon.properties discussion
Analyst Client User Guide	Available upon installation. Panopticon Real Time documentation for users with a Viewer role which consists of: • viewing and analysing of workbooks • creating, monitoring, and deleting of alerts Available upon installation.
User Community	Link to the Panopticon User Community page.

Data Analytics Documentation	Link to the Altair Data Analytics Documentation page.
Altair Documentation	Link to product documentation in the Altair Community page.

[APPENDIX]

YAML

YAML is a standard configuration file format and is used in Panopticon's <appdata>/security.yml file. Technically it's equivalent to the Java properties file format but has the advantage of being easier to read (for humans) and avoids a lot of repetition.

A YAML file is just a text file that you can edit with any text editor but note that in YAML indentation has meaning. Be careful to preserve indentation (i.e., spaces at the start of lines) when you edit or copy YAML. YAML also has facilities to break long values over multiple lines and other nice features.

See https://en.wikipedia.org/wiki/YAML for more information.

Here's an example of some properties in a Java properties file:

```
access.default.roles=VIEWER
access.designer.groups=analysts,reviewers
access.designer.users=bob@company.org
```

YAML uses colon to separate names and values, but that's really all you need to change to convert to a valid YAML file:

```
access.default.roles: VIEWER
access.designer.groups: analysts, reviewers
access.designer.users: bob@company.org
```

YAML lets you collect a common name prefix on one line, if you indent the lines below. So, this is equivalent to the preceding:

```
access:
   default.roles: VIEWER
   designer.groups: analysts, reviewers
   designer.users: bob@company.org
```

You can keep doing this:

```
access:
   default.roles: VIEWER
   designer:
       groups: analysts, reviewers
       users: bob@company.org
```

This saves a lot of space and makes the configuration easier to read. Especially when you have long property names as Spring Security seems to favor, for example:

```
spring.security:
    saml2.relyingparty.registration:
    okta-saml:
        assertingparty:
        metadata-uri: https://server.com/metadata
        signing.credentials:
        private-key-location: /etc/key.pem
        certificate-location: /etc/cert.p12
```

The corresponding Java properties:

```
spring.security.saml2.relyingparty.registration.okta-saml.assertingparty.metadata-uri=https\://server.com/metadata spring.security.saml2.relyingparty.registration.okta-saml.signing.credentials.private-key-location=/etc/key.pem spring.security.saml2.relyingparty.registration.okta-saml.signing.credentials.certificate-location=/etc/cert.p12
```

CORS

If you need to configure a Cross-Origin Resource Sharing (CORS) filter for Panopticon, add properties for it in <appdata>/security.yml.For example:

```
cors:
   allowed-origins: http://host.sub.company.com:666, http://localhost:9000
   exposed-headers:
        - Access-Control-Allow-Origin
        - Access-Control-Allow-Credentials
   allowed-headers:
        - UTC-Offset
        - Content-Type
        # ... more headers
        - Authorization
   allowed-methods: GET, POST, HEAD, OPTIONS, PUT, DELETE
   allow-credentials: true
```

REST AND AUTHENTICATION

If you want to call REST endpoints on the Panopticon server programmatically, you typically need to authenticate. You have a few options for this:

- API Tokens
- Basic Authentication
- Session
- Authentication Cookie

API Tokens

This is the recommended option. Log in to Panopticon in the web UI as an administrator user, go to the **System > API Tokens** tab, and generate a new token. Copy the displayed value and paste in a secured location as it cannot be recovered later, and use it as a bearer token in your REST call:

```
curl http://company.org/panopticon/server/rest/server/myself \
   -H "Authorization: Bearer <api-token-value>"
```

Basic Authentication

This option works only if you use username and password authentication, either against <appdata>/users.xml or against LDAP. This mode also enables basic authentication, so you can either:

```
curl http://company.org/panopticon/server/rest/server/myself \
   -H "Authorization: Basic <base64-credentials>"
Or use the cURL shortcut:
```

```
curl http://company.org/panopticon/server/rest/server/myself \
   -u <username>:<password>
```

Session

This option works for any authentication method and is useful if you want to impersonate a normal user or simulate an entire session. Some authentication methods, like OAuth and SAML, are designed to prevent automated logins, so this option is less useful for them. For instance, you would need to interactively log on to a browser first.

An authentication is valid for the duration of the user session, so an alternative to passing the username and password on every call is to authenticate once and then keep track of the session ID cookie:

```
curl -i http://company.org/panopticon/login \
   -d "username=<username>&password=<password>"
```

The response is a redirect, but you can ignore that, all you need is the session ID:

```
HTTP/1.1 302
...
Set-Cookie: SESSION=YjUxN2JhNmMtOGFmNy00YWRiLTgzNmUtNDYzMDhmNGQyYzdm;
Path=/panopticon; HttpOnly; SameSite=Lax
Location: /panopticon/login_success_info
...
```

Then pass that on subsequent REST calls:

```
curl http://company.org/panopticon/server/rest/server/myself \
   -H "Cookie: SESSION=YjUxN2JhNmMtOGFmNy00YWRiLTqzNmUtNDYzMDhmNGQyYzdm"
```

The server can be configured to rotate session IDs occasionally, so for lengthy sessions you should look for new Set-Cookie headers with a new ID.

Authentication Cookie

This option should be avoided, but the server considers a valid authentication JWT cookie to be proof of identity too. Because these cookies expire and can get invalidated by server for several reasons, you should only use them if you are trying to impersonate a normal user, and you are not using username and password authentication. Just grab one from a browser where you are already logged in against Panopticon.

PROPERTIES: PANOPTICON

The majority of configuration options for the server are set in the Panopticon.properties file in the AppData directory (e.g., /etc/panopticon/appdata). If this file does not exist when the server starts, it will create it with all default values. When the server starts after an upgrade, it may add new properties and remove deprecated ones.

You can optionally move sensitive properties like passwords and URLs from this file, where they are stored in clear text, into a file named Secret.properties in the same directory. The Secret.properties file stores values encrypted, and you can manage it with PCLI. A property can only be defined in one of these files at a time.

The following properties can be set in the property files:

Property	Alert
Attribute	alert.creation.only.by.administrators
Description	Enable or disable whether only the Administrators can create alerts.
Default Value	false
Property	Alert
Attribute	alert.detailed.logging
Description	Enables or disables extra alert logging.
Default Value	false
Property	Alert
Attribute	alert.event.auto_resolve
Description	When set to false , the system will not automatically resolve events when alert conditions are no longer true.
Default Value	true
Property	Alert
Attribute	alert.event.history.days
Description	Days to keep closed alert events before deletion. NOTE: Open alert events are never deleted.
Default Value	7
Property	Bookmark Administration
Attribute	bookmark.administration.only.by.administrators
Description	Set to true if only Administrators should be able to manage bookmarks.
Default Value	false
Property	Bookmark Administration
Attribute	bookmark.show_shared

Description	Allows private bookmarking. If set to true , all of the users will be able to view each other's bookmarks. If set to false , bookmarks will only be viewed by the one who created them.
Default Value	true
Property	Cache
Attribute	cache.data.datasource.enabled
Description	Enable or disable the caching of the data source.
Default Value	true
Property	Cache
Attribute	cache.data.datasource.size
Description	The data source cache size.
Default Value	100
Property	Cache
Attribute	cache.data.datasource.type
Description	The data source cache type. Allowed values: MEMORY, NONE
Default Value	MEMORY
Property	Cache
Attribute	cache.data.datatable.enabled
Description	Enable or disable the caching of the data table.
Default Value	true
Property	Cache
Attribute	cache.data.datatable.size
Description	The data table cache size.
Default Value	100
Property	Cache
Attribute	cache.data.datatable.type
Description	The data table cache type.Allowed values: MEMORY, NONE
Default Value	MEMORY
Property	Cache
Attribute	cache.data.query.enabled
Description	Enable or disable the caching of data query.
Default Value	true
Property	Cache
Attribute	cache.data.query.size

Default Value	100
Property	Cache
Attribute	cache.data.query.type
Description	The data query cache type. Allowed values: MEMORY , NONE
Default Value	MEMORY
Property	Cache
Attribute	cache.plugin.id
Description	The ID of the plugin that will be used to store data. Possible values: BinaryTableFile-Cache .
Default Value	BinaryTableFile-Cache
Property	Cache
Attribute	cache.purge.condition
Description	Defines the condition for when the cache will be purged. Allowed values: NONE, MEMORY
Default Value	MEMORY
Property	Cache
Attribute	cache.purge.condition.memory.threshold
Description	Defines a percentual memory threshold for cache purging, when the cache.purge.condition = MEMORY.
Default Value	80
Property	Cache
Attribute	cache.purge.enabled
Description	Enables scheduled cache purging.
Default Value	true
Property	Cache
Attribute	cache.schedule.clear.enabled
Description	Enable the cache clearing schedule. This is scheduling the clear cache operation which will remove all the expired cache entries.
Default Value	true
Property	Cache
Attribute	cache.service.enabled
Description	Enables or disables the service cache.
Default Value	true
Property	Cache
Attribute	cache.service.type

Description	The service cache mechanism being used.
Default Value	IN_MEMORY
Property	Client Cache
Attribute	client.cache.control.age.max
Description	Controls the cache-control max-age header for static content.
Default Value	31536000
Property	Client File Path Upload
Attribute	client.filepath.upload.disabled
Description	If set to true , the Upload File option will not be available.
Default Value	false
Property	Client Data
Attribute	client.data.load.transport
Description	Configure the transportation protocol for loading data from the Web client. Possible values: WEBSOCKET, LONG_POLLING.
	NOTE: This property has been deprecated. Refer to <u>Setting the Transportation Protocol</u> for more information.
Default Value	WEBSOCKET
Property	Server Cluster
Attribute	cluster.bully.bind
Description	The URL of the server in bully mode. This should be the URL to the panopticon server web application on the server itself, by which is reachable from the other servers.
Default Value	
Property	Server Cluster
Attribute	cluster.bully.boot
Description	Comma-separated list of server URLs in bully mode. At least one of these servers should be running at all times for the bully mode to work correctly. The URLs should be the same as the cluster.bully.bind value on each boot server.
Default Value	
Property	Server Cluster
Attribute	cluster.bully.id
Description	The unique server ID in bully mode. Can be any string, but do not change it after the server has participated in a cluster the other servers will store it and expect it to identify the same server in the future. The running server with the lowest ID lexicographically will be leader.
Default Value	
Property	Server Cluster

Attribute	cluster.fixed.leader
Description	The leader URL in fixed mode. This should be the URL to the panopticon server web application on the preset leader server, by which it is reachable from the follower servers. Leave blank on the leader server itself.
Default Value	
Property	Server Cluster
Attribute	cluster.kubernetes.container_name
Description	Optionally name of the container that runs the Panopticon server, if the pod also runs other containers. If left blank, the first container will be used.
Default Value	
Property	Server Cluster
Attribute	cluster.kubernetes.id
Description	Set to the name of the pod that runs the container.
Default Value	(blank)
Property	Server Cluster
Attribute	cluster.kubernetes.label_selector
Description	Standard Kubernetes label selector that should only match the pods that are running the server.
Default Value	
Property	Server Cluster
Attribute	cluster.kubernetes.peer_path
Description	Path to the web application on each server. For example, "panopticon/", or "/" if you have deployed to Tomcat's root.
Default Value	
Property	Server Cluster
Attribute	cluster.mode
Description	NONE (default), FIXED, BULLY, or KUBERNETES
Default Value	
Property	Server Cluster
Attribute	cluster.shared.secret
Description	Any alphanumeric string. Secret used to encrypt a challenge in peer-to-peer communication handshake. Needs to be the same, and non-empty, on all connected servers.
Default Value	
Property	Server Cluster
Attribute	cluster.store.type

Description	The type of storage to use for cluster-shared data. By default, this data is stored in a server-private directory in <appdata> and not shared with cluster peers. See the Synchronizing Tokens section for more information.</appdata>
Default Value	DIRECTORY
Property	Server Cluster
Attribute	cluster.store.zookeeper.connect
Description	A standard ZooKeeper connect string: a comma-separated list of one or more ZooKeeper servers in <pre><host>:<port> format</port></host></pre> . NOTE: This property is not automatically added to Panopticon.properties, so you need to add it manually.
Default Value	
Property	Altair Al Hub Connector Endpoint Listing
Attribute	connector.aihub.client.id
Description	Application (client) ID assigned at the Altair Al Hub.
Default Value	
Property	Altair Al Hub Connector Endpoint Listing
Attribute	connector.aihub.client.secret
Description	Your application's client secret created at the Altair Al Hub.
Default Value	
Property	Altair Al Hub Connector Endpoint Listing
Attribute	connector.aihub.grant_type
Description	The grant type to be used to make token request.
Default Value	refresh_token
Property	Altair Al Hub Connector Endpoint Listing
Attribute	connector.aihub.url
Description	The root URL to Altair Al Hub, where token and endpoint request are sent.
Default Value	
Property	AMPS Connector Custom Authenticator
Attribute	connector.amps.authenticators
Description	This property is required when a custom authenticator is needed for AMPS connection. A custom authenticator needs be implemented as java .JAR file. The property excepts a JSON object, where key is fully qualified name of the Authenticator Java class, and values are list of constructor parameter names, e.g., "{"com.panopticon.examples.amps.AMPSClientAuthenticator":["Us er", "Shared Key"]}"
Default Value	
Property	Connector Column Generator
Attribute	connector.column generator.max columns

Description	Controls the maximum number of columns generated by the text- based connectors/parsers. Currently only used by JSON connector and parser.
Default Value	100
Property	Connector File Path
Attribute	connector.common.filepath.link.disabled
Description	If set to true , the <i>Link to File</i> option will not be available.
Default Value	false
Property	Host Lookup
Attribute	connector.kdb.host.lookup.script
Description	Full path of the shell script file that is accessible on the server. When set, before making a new kdb+ connection, this script is executed to get the host info. This property helps in overriding connection details entered inside the kdb+ connector UI centrally, and may help when different authentications are set at kdb+ like Kerberos/Custom etc. The output of this script is expected to be a JSON object like below. { "host": "localhost", "port": 5001, "username": "", "password": "" } NOTE: Starting with the 21.2 release, the the kdb+ connection pool feature of Panopticon (kdb.connection.pool.xx) can be used together with the host lookup. So any new connection request from the pool, will first execute the script set here, to get the host info before the pool is looked up for available connections. Examples: For Windows connector.kdb.host.lookup.script=E://Data/host.bat For Linux connector.kdb.host.lookup.script=/etc/panopticon/appdata/host.sh
Default Value	
Property	Host Lookup
Attribute	connector.kdb.host.lookup.script.arguments
Description	Delimited set of arguments to be passed to the script when it is executed. '{host}, {port}, {userid}, {password}' is the default value, and these parameters are mapped to respective settings in the connector UI i.e., the value entered against these settings in the connector UI are passed as arguments to the script. This property can be extended or updated if you want to pass other datatable parameters as arguments. System parameter like { _user_id} or { _workbook_folder}, if added to the data table, can also be used. If the value of some parameter is null or empty at the time of execution of the script, two single quotes are passed (") against that parameter, this is to make sure that arguments count matches the arguments set at this
	property.
Default Value	{host},{port},{userid},{password}

A 11 11 1	
Attribute	connector.kdb.host.lookup.script.arguments.delimiter
Description	Used to split the arguments set at above property.
Default Value	,
Property	Host Lookup
Attribute	connector.kdb.host.lookup.script.timeout
Description	The timeout (in milliseconds) to wait for the host lookup script to run and return the host info.
Default Value	5000
Property	Amazon Kinesis – Data Streams connector
Attribute	connector.kinesis.datastreams.accesskeyid
Description	The Access Key ID from the AWS account.
Default Value	
Property	Amazon Kinesis – Data Streams connector
Attribute	connector.kinesis.datastreams.secretaccesskey
Description	The Secret Access Key ID from the AWS account.
Default Value	
Property	OAuth Token URL
Attribute	connector.oauth.tokenurl
Description	Sets the server-wide token URL.
Default Value	http\://localhost\:5000/oauth/token
Property	OneDrive connector
Attribute	connector.onedrive.client.id
Description	Application (client) ID assigned by the Azure administration portal.
Default Value	
Property	OneDrive connector
Attribute	connector.onedrive.client.secret
Description	Your application's client secret created in the application registration portal.
Default Value	
Property	OneDrive connector
Attribute	connector.onedrive.root.url
Description	The Microsoft Graph API root URL.
Default Value	https\://graph.microsoft.com/v1.0/me/drive/root
Property	OneDrive connector
Attribute	connector.onedrive.tenant.id

Description	Controls who can sign into the application. The allowed values are:
	common - for both Microsoft accounts and work or school accounts
	organizations - for work or school accounts only
	consumers - for Microsoft accounts only tenant - identifiers such as the tenant ID or domain name
Default Value	tenant - Identifiers such as the tenant ID of domain frame
Property	Python connector
Attribute	connector.python.host
7 111 12 410	
Description	The default Python Pyro instance host address. NOTES:
	<pre>For connector.python.host, connector.python.password, connector.python.port, and connector.python.serializertype properties:</pre>
	• If set in the Panopticon.properties file, these fields will be hidden in the Python connector and will be applied to the Python transform as well.
	These default Panopticon Real Time connection properties will be applied at runtime.
	These default Panopticon Real Time connection properties will override old Python connection settings.
Default Value	
Property	Python connector
Attribute	connector.python.password
Description	The default HMAC Key.
Default Value	
Property	Python connector
Attribute	connector.python.port
Description	The default Python Pyro host port.
Default Value	
Property	Python connector
Attribute	connector.python.serializertype
Description	The default Python serialization type. Possible values are serpent or pickle .
Default Value	
Property	Rserve connector
Attribute	connector.rserve.host
Description	The default Rserve host address. NOTES:
	<pre>For connector.rserve.host, connector.rserve.password, connector.rserve.port, and connector.rserve.userid properties:</pre>
	• If set in the Panopticon.properties file, these fields will be hidden in the Rserve connector and will be applied to the R transform as well.

	These default Panopticon Real Time connection properties will be applied at runtime.
	These default Panopticon Real Time connection properties will override old Rserve connection settings.
Default Value	
Property	Rserve connector
Attribute	connector.rserve.password
Description	The default password that will be used to connect to the Rserve service.
Default Value	
Property	Rserve connector
Attribute	connector.rserve.port
Description	The default Rserve host port.
Default Value	
Property	Rserve connector
Attribute	connector.rserve.userid
Description	The default user Id that will be used to connect to the Rserve service.
Default Value	
Property	Data Store
Attribute	datastore.connection.schema
Description	Name of the database schema to be used for creating or managing objects inside database.
Default Value	dbo
Property	Data Store
Attribute	datastore.type
Description	Controls which data store connector should be used. Valid values are MonetDB ", MSSQLServer and PostgreSQL .
Default Value	MonetDB
Property	Data Store
Attribute	datastore.connection.jndi
Description	JNDI resource name for the connection e.g., jdbc/MyDB . More details on how to configure JNDI is at <u>JNDI Connection Details</u> section.
Default Value	
Property	Data Store
Attribute	datastore.connection.url
Description	JDBC connection URL for the database e.g., jdbc:monetdb://localhost:49153/PanopticonDataStore This property value is discarded If datastore.connection.jndiproperty is set.
Default Value	

Property	Data Store
Attribute	datastore.connection.driverclassname
Description	Fully qualified Java class name of the JDBC driver used for the connection.
Default Value	org.monetdb.jdbc.MonetDriver
Property	Data Store
Attribute	datastore.connection.username
Description	Username for the connection. Only required when using connection URL.
Default Value	
Property	Data Store
Attribute	datastore.connection.password
Description	Password for the connection. Only required when using connection URL.
Default Value	
Property	REST Documentation
Attribute	documentation.enabled
Description	Enable or disable the OpenAPI Specification documentation for the REST interface.
Default Value	false
Property	Alert
Attribute	email.address
Description	The email address where the alert will be sent from.
Default Value	
Property	Email
Attribute	email.host
Description	The host name used by the email server.
Default Value	
Property	Alert
Attribute	email.password
Description	The email password, if available. NOTE: When using a Gmail account, you must use an app password to authenticate with the Gmail SMTP server. See Sign in with app passwords for more information.
Default Value	
Property	Email
Attribute	email.port
Description	The port number used by the email server.
Default Value	

Property	Email
Attribute	email.security.mode
Description	The security mode used when sending emails. Possible values: NONE , SSL , TLS .
Default Value	NONE
Property	Email
Attribute	email.sender_name
Description	Sender Name alias to use when sending email.
Default Value	
Property	Email
Attribute	email.username
Description	Email account username.
Default Value	
Property	Error Message
Attribute	error.default.message
Description	Custom error message to be displayed inside visualizations when there is a problem with loading data from a data table.
Default Value	
Property	Report File Copies
Attribute	export.filesystem_copy.path
Description	 If set to a directory, whether it exists or not, then: Operations that email CSV, Excel, HTML, Image, PDF, or ZIP files (i.e., scheduled tasks) will also write a copy of the file to the specified directory.
	 Operations that generate and return PDF, CSV, or ZIP files (e.g., Create PDF Report toolbar button on a dashboard) will also write a copy of the file to the specified directory.
	If not set (blank), the server works the same way as before.
	NOTE: To get report file copies, you also need to specify which services to get copies from using the export.filesystem_copy.services property.
Default Value	(blank, meaning disable file copies)
Property	Report File Copies
Attribute	export.filesystem_copy.services
Description	A list of reporting services that you want file copies from, assuming that you have set export.filesystem_copy.path, for example, GetAdhocPdfService, GetExcelService, or the special value ALL to get copies from all reporting services. The easiest way to find the name for a particular service is to temporarily add value ALL to the list, run the report, then check the created file copy's information.
Default Value	(blank, meaning copies from no services)
Property	Image export

Description The default height for an exported image. Property Image export Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 60000 Property kdb+ Connection Pooling Attribute kab.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+server that use the same username, password, TLS flag, and timeoutly, so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling Attribute kdb-connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Soolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Attribute licensing Attribute license.hwu.hosted.authorization.password Description Password to the Altair One account.	Attribute	export.image.height
Property Image export Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 30000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+servers that use the same username, password, TLS flag, and timeoutly, so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool is that it can reduce latency. Setting this property to 0 disables the connection instance created. Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Description	The default height for an exported image.
Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value 1censel, hwu.hosted.authorization.password	Default Value	768
Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool is that it can reduce latency. Setting this property to 0 disables the connection instance created. Default Value 10 Property kdb+ Connection.pool.tt1 Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Property	Image export
Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 30000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. Abenefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb-connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing	Attribute	export.image.width
Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 30000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Description	The default width for an exported image.
Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute licensing	Default Value	1024
Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Property	File Upload
Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 60000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in or the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.tt1 Description Time to live in milliseconds for each connection instance created. Default Value 1 icense.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Attribute	file.upload.size.max.bytes
Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+servers that use the same username, password, TLS flag, and informeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute licensing Attribute license.hwu.hosted.authorization.password	Description	
Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Default Value	30000000
Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Attribute kdb. connection Pooling Attribute bescription The maximum number of connections that will be kept open for reuse for each kdb-server (among kdb+ servers that use the same username, password, TLS flag, and imeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb- Connection Pooling Attribute kdb. connection.pool.ttl Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute 1 icense.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute 1 icense.hwu.hosted.authorization.password	Property	Copy Image
than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Robberty Attribute kdb+ Connection Pooling Attribute Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute 1 icense.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute 1 icense.hwu.hosted.authorization.password	Attribute	image.client.timeout
Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Description	
Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Default Value	600000
Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute 1 icense.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute 1 icense.hwu.hosted.authorization.password	Property	kdb+ Connection Pooling
server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Attribute	kdb.connection.pool.max.size
Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Description	server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency.
Attribute kdb.connection.pool.ttl Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Default Value	10
Description Time to live in milliseconds for each connection instance created. Default Value 30000 Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Property	kdb+ Connection Pooling
Default Value Property Licensing Attribute Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value False Property Licensing Attribute license.hwu.hosted.authorization.password	Attribute	kdb.connection.pool.ttl
Property Licensing Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Description	Time to live in milliseconds for each connection instance created.
Attribute license.hwu.hosted Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Default Value	30000
Description Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Property	Licensing
you wish to use managed licensing. Default Value false Property Licensing Attribute license.hwu.hosted.authorization.password	Attribute	license.hwu.hosted
Property Licensing Attribute license.hwu.hosted.authorization.password	Description	
Attribute license.hwu.hosted.authorization.password	Default Value	false
•	Property	Licensing
Description Password to the Altair One account.	Attribute	license.hwu.hosted.authorization.password

Default Value	
Property	Licensing
Attribute	license.hwu.hosted.authorization.token
Description	An authorization token generated through the Altair One admin portal. Used to authorize a machine to the managed Altair Units system.
Default Value	
Property	Licensing
Attribute	license.hwu.hosted.authorization.username
Description	Username to the Altair One account.
Default Value	
Property	Licensing
Attribute	license.hwu.uri
Description	The path where the License Server is running e.g., 6200@191.255.255.0 where the syntax is PORTNUMBER@HOST. If multiple servers are specified, use the ';' semicolon separator sign for Windows and the ':' colon separator sign for Linux.
	NOTE: If value is not set in the Panopticon.properties, the environment variable ALTAIR_LICENSE_PATH serves as the backup path and will be used.
Example	For Windows:
	license.hwu.uri=6200@192.168.5.51;6200@192.168.5.52
	For Linux: license.hwu.uri=6200@192.168.5.51:6200@192.168.5.52
Default Value	
Property	Licensing
Attribute	license.hwu.use client timezone
Description	Determines how the ALJDK should process the timezone details. If set to true , the ALJDK will process the timezone details sent by Panopticon client to the Panopticon server. If set to false , the Panopticon server timezone is used.
Default Value	true
Property	Licensing
Attribute	license.mode
Description	The license mode. Possible values are FILE or HWU . To use the Altair Units license, set this property to HWU.
Default Value	FILE
Property	Log level
Attribute	logger.level.file
Description	Controls the level that is logged to file.

Default Value	INFO
Property	Server Metrics
Attribute	metrics.authorization.level
Description	Specifies the required authorization level to get server metrics. Available values are ANONYMOUS , VIEWER , DESIGNER , ADMINISTRATOR . NOTE: This property is case sensitive.
Default Value	ADMINISTRATOR
Property	Server Metrics
Attribute	metrics.collection.rate
Description	Specifies the rate at which metrics are collected in milliseconds.
Default Value	1000
Property	Server Metrics
Attribute	metrics.file.flush.rate
Description	Specifies how often metrics should be saved to disk in milliseconds. Only used if the metrics.publisher.type is set to FILE.
Default Value	10000
Property	Server Metrics
Attribute	metrics.memory.queue.size
Description	Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY .
Default Value	100
Property	Server Metrics
Attribute	metrics.publisher.configuration
Description	Specifies the id for which metric publisher configuration to use.
Default Value	
Property	Server Metrics
Attribute	metrics.publisher.type
Description	Specifies the current metric publisher that is used. Available values are NONE , MEMORY , FILE , EMAIL , INFLUX_DB , JDBC , KAFKA , KDB , MQTT , REST , TEXT .
Default Value	MEMORY
Property	Bookmarks repository
Attribute	repository.import.bookmarks.paths
Description	Will import bookmarks from the old format into the repository. Will override any existing bookmarks inside the repository. Must be set to an absolute path. Only bookmarks for workbooks that exists inside the repository will be imported.
Default Value	

Property	Workbook repository
Attribute	repository.migrate.archive.path
Description	Use this property if you have an older (pre 2020) server and wish to start the new server with the same workbook content as the old one, and also to import the workbooks' change history from the old server. Set the property to the absolute path to the old server's <appdata>/Archive/ directory, delete the new server's <appdata>/.repository/ directory, and start the new server. You typically use this property with the repository.migrate.workbooks.path property. See also the section on content migration.</appdata></appdata>
Example	/etc/panopticon/appdata/Archive
Default Value	
Property	Bookmarks repository
Attribute	repository.migrate.bookmarks.path
Description	Will migrate bookmarks from the old format into the repository if there are no bookmarks inside the repository yet. Set to an absolute path or to the default Bookmarks folder. Only bookmarks for workbooks that exists inside the repository will be migrated.
	NOTE: If you do not wish to migrate bookmarks or already have bookmarks in the repository, set this property to blank to avoid a warning on startup.
Default Value	Bookmarks
Property	Workbook repository
Attribute	repository.migrate.data.extracts.path
Description	Starting with version 21.0, data extracts are stored inside the repository. If this property is set to GlobalCaches (default value), or to an absolute path, the server will migrate data extracts into the repository on startup as long as the repository does not contain any previous data extracts. NOTE: If you do not wish to migrate data extracts or already have data extracts in the repository, set this property to blank to avoid a warning on startup.
Default Value	GlobalCaches
Property	Data Templates Repository
Attribute	repository.migrate.datatable.templates.path
Description	Will migrate data table templates from the old format into the repository if there are no data table templates inside the repository yet. Set to an absolute path or to the default Datatables folder. NOTE: If you do not wish to migrate data table templates or already have data table templates in the repository, set this property to blank to avoid a warning on startup.
Default Value	Datatables
Property	Themes repository
Attribute	repository.migrate.themes.path
Description	Will migrate themes from the old format into the repository if there are no themes inside the repository yet. Set to an absolute path or to the default Themes folder.
	NOTE: If you do not wish to migrate themes or already have themes in the repository, set this property to blank to avoid a warning on startup.

Default Value	Themes
Property	Workbook repository
Attribute	repository.migrate.workbooks.path
Description	Use this property if you have an older (pre 2020) server and wish to start the new server with the same workbook content as the old one. Set the property to the absolute path to the old server's <appdata>/Workbooks/ directory, delete the new server's <appdata>/.repository/ directory, and start the new server. See also the section on content migration.</appdata></appdata>
Example	/etc/panopticon/appdata/Workbooks
Default Value	
Property	Repository
Attribute	repository.startup.apply.permissions.clean
Description	Use this property with the repository.startup.apply.permissions.path to reset all existing workbook permissions on the server before applying the template. If you set it to true , the server will remove all permissions, then give users full permissions to their private folders, and the "Everyone" group full permissions to public folders.
Default Value	false
Property	Repository
Attribute	repository.startup.apply.permissions.create
Description	Use this property with the repository.startup.apply.permissions.path to create empty workbook folders for any folders that are in the template file but do not yet exist on the server. If you don't set it to true , these folders from the template will be ignored.
Default Value	true
Property	Repository
Attribute	repository.startup.apply.permissions.path
Description	Use this property to make the server apply workbook folder permissions from a template JSON file on startup. Workbook folder permissions in the template will overwrite any existing permissions on the server. This property will not migrate permissions from an older (pre 2020) server, you need to use the PCLI convertpermissions to generate a template file from the old permissions first. See also repository.startup.apply.permissions.clean and repository.startup.apply.permissions.create.
Default Value	
Property	Repository
Attribute	repository.startup.filesystemcheck
Description	If set to true , server runs on startup to verify the repository integrity and reports any of the following issues: • a deleted /HEAD file, • a modified /HEAD, • a modified /refs/heads/master file,

	 any file deleted inside /objects/ (e.g., /objects/94/443eec118fb8bb2021071896ff7d386a9c9518),
	• any file modified inside /objects/.
	NOTE: There may be dangling files in the /objects/ directory or those that are not in use. These files are typically results of failed saves and/or sync conflicts. The check may or may not detect deleted or modified dangling files, but that is not critical.
Default Value	false
Property	Repository Import
Attribute	repository.startup.import.paths
Description	NOTE: Use this property to make the server import content at startup. This is imported on top of the existing content and will always overwrite anything that is already there. This property can be useful for example, if you have multiple servers with different content but you want the latest version of a standard set of workbooks to be deployed on all of them. This property only has an effect on a stand-alone or leader server.
	This property is the list of paths to directories and files, separated by the system specific path separator ";" on Windows and ":" on Linux. Each directory is scanned and imported keeping its local tree structure.
	For example, workbooks to be imported are placed in a folder and in this property, the absolute path to that folder is specified.
	ADDITIONAL NOTES:
	• User-specific folders (e.g., "~john/") can be targeted this way, but only if they already exist on the server.
	Bundles (exz files) directly listed in the property or found in directories listed are also imported, but always to the root, with their internal structure preserved.
	Files that are not legacy workbooks or bundles are ignored.
	The same set of workbooks will get imported over and over (startup, user edit, restart) and for bundles (nothing changes in the history the second time), but legacy workbooks change their meta data.
	The import always overwrites local changes (it resets the workbooks in the repository).
	Permissions are not supported, and any folders created will have "SYSTEM" as owner.
Default Value	
Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.entry.delimiter
Description	The delimiter that separates the configuration entries. This property will only affect incoming parameters.
Default Value	, (Comma)
Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.optional
Description	The parameters that could be updated with certain cookie values. This property will only affect incoming parameters. The operation will not fail if the cookie values are not present in the request. The parameters will keep their default value instead of the configured cookie value if the cookie is not present. The property should be formatted as follows: Parameter name (Value delimiter) Cookie name.
Default Value	

_	
Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.required
Description	The parameters that are required to be updated with certain cookie values. This property will only affect incoming parameters. The operation will fail if configured cookie values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Cookie name.
Default Value	
Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.value.delimiter
Description	The delimiter that separates the parameter name and the cookie name. This property will only affect incoming parameters.
Default Value	: (Colon)
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.entry.delimiter
Description	The delimiter that separates the configuration entries. This property will only affect incoming parameters.
Default Value	, (Comma)
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.optional
Description	The parameters that could be updated with certain header values. This property will only affect incoming parameters. The operation will not fail if the header values are not present in the request. The parameters will keep their default value instead of the configured header value if the header is not present. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.required
Description	The parameters that are required to be updated with certain header values. This property will only affect incoming parameters. The operation will fail if a configured header values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.value.delimiter
Description	The delimiter that separates the parameter name and the header name. This property will only affect incoming parameters.
Default Value	(0.1.)
Delault value	: (Colon)
Property	Response parameter mapping

Description	The delimiter that separates the configuration entries. This property will only affect outgoing parameters.
Default Value	, (Comma)
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.optional
Description	The parameters that could be updated with certain Header values. This property will only affect outgoing parameters. The operation will not fail if the Header values are not present in the request. The parameters will keep their default value instead of the configured Header value if the Header is not present. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.required
Description	The parameters that are required to be updated with certain Header values. This property will only affect outgoing parameters. The operation will fail if configured Header values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.value.delimiter
Description	The delimiter that separates the parameter name and the Header name. This property will only affect incoming parameters.
Default Value	: (Colon)
Property	REST
Attribute	rest.response.error.stacktrace.included
Description	Include the error stack trace in REST responses.
Default Value	false
Property	Compatibility
Attribute	server.force_downgrade
Description	The server normally refuses to start if it detects that the AppData directory has been used by a server with a newer version. This is because downgrading content and other AppData files is not supported and can cause irreversable issues. You can set this property to true to force the server to start anyway, but it is strongly recommended that you do not.
Default Value	false
Property	Email
Attribute	server.host
Description	The server endpoint address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example:

	server.host=http://www.company.com/dashboards/
Default Value	
Property	PDF and Image generation
Attribute	server.host.internal
Description	The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/
Default Value	
Property	Server
Attribute	server.id
Description	Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated.
Default Value	
Property	SOAP
Attribute	soap.enabled
Description	Enable or disable the SOAP interface
Default Value	true
Default Value Property	true Data table regression testing
Property	Data table regression testing
Property Attribute	Data table regression testing startup.regression.datatable.exclude.folders Comma-separated list of folders that will be excluded in the testing. Use this property in combination with the startup.regression.datatable.include.folders property to control which workbooks to include in the testing. For example, you can set startup.regression.datatable.include.folders to "pub\\" and startup.regression.datatable.exclude.folders to
Property Attribute Description	Data table regression testing startup.regression.datatable.exclude.folders Comma-separated list of folders that will be excluded in the testing. Use this property in combination with the startup.regression.datatable.include.folders property to control which workbooks to include in the testing. For example, you can set startup.regression.datatable.include.folders to "pub\\" and startup.regression.datatable.exclude.folders to
Property Attribute Description Default Value	Data table regression testing startup.regression.datatable.exclude.folders Comma-separated list of folders that will be excluded in the testing. Use this property in combination with the startup.regression.datatable.include.folders property to control which workbooks to include in the testing. For example, you can set startup.regression.datatable.include.folders to "pub\\" and startup.regression.datatable.exclude.folders to "pub\\" and "pub\" and "pub\\" and "pub\\" and "pub\\" and "pub\" a
Property Attribute Description Default Value Property	Data table regression testing startup.regression.datatable.exclude.folders Comma-separated list of folders that will be excluded in the testing. Use this property in combination with the startup.regression.datatable.include.folders property to control which workbooks to include in the testing. For example, you can set startup.regression.datatable.include.folders to "pub\\" and startup.regression.datatable.exclude.folders to "pub\\" and startup.regression.datatable.exclude.folders to "pub\\" bub\\ examples\pub\\ temp\\".
Property Attribute Description Default Value Property Attribute	Data table regression testing startup.regression.datatable.exclude.folders Comma-separated list of folders that will be excluded in the testing. Use this property in combination with the startup.regression.datatable.include.folders property to control which workbooks to include in the testing. For example, you can set startup.regression.datatable.include.folders to "pub\\" and startup.regression.datatable.exclude.folders to "pub\\" and startup.regression.datatable.exclude.folders to "pub\\examples\pub\\temp\\". Data table regression testing startup.regression.datatable.include.folders
Property Attribute Description Default Value Property Attribute	Data table regression testing startup.regression.datatable.exclude.folders Comma-separated list of folders that will be excluded in the testing. Use this property in combination with the startup.regression.datatable.include.folders property to control which workbooks to include in the testing. For example, you can set startup.regression.datatable.include.folders to "pub\\" and startup.regression.datatable.exclude.folders to "pub\\examples\\pub\\temp\\\". Data table regression testing startup.regression.datatable.include.folders Comma-separated list of folders to test. The default is blank, which means the root folder and all workbooks will be tested. If you list folders here, then only the data tables in workbooks in these folders will be tested, unless also excluded. Folder paths should include a trailing backslash, and you need to use double backslashes since this is the escape character in Java property files. For example, to only include prod and qa\final, you should set the property to
Property Attribute Description Default Value Property Attribute Description	Data table regression testing startup.regression.datatable.exclude.folders Comma-separated list of folders that will be excluded in the testing. Use this property in combination with the startup.regression.datatable.include.folders property to control which workbooks to include in the testing. For example, you can set startup.regression.datatable.include.folders to "pub\\" and startup.regression.datatable.exclude.folders to "pub\\examples\\pub\\temp\\\". Data table regression testing startup.regression.datatable.include.folders Comma-separated list of folders to test. The default is blank, which means the root folder and all workbooks will be tested. If you list folders here, then only the data tables in workbooks in these folders will be tested, unless also excluded. Folder paths should include a trailing backslash, and you need to use double backslashes since this is the escape character in Java property files. For example, to only include prod and qa\final, you should set the property to

Attribute	startup.regression.datatable.runonce
Description	If set to true , the server will run a data table regression test during the next startup. The property is immediately reset to false , so you need to set it to true again to run another test. NOTE: You can set the property through an environment variable if you want to force the
Default Value	server to run it on every startup. false
Property Property	Authorization
Attribute	statistics.authorization.level
Description	Allows users to set the authorization level for the statistics and diagnostic REST services. Possible values include: ANONYMOUS , VIEWER , DESIGNER , ADMINISTRATOR . NOTE : This property is case sensitive.
Default Value	ADMINISTRATOR
Property	Statistics
Attribute	statistics.accumulated.enabled
Description	By default, the server accumulates statistics from every run into files in <appdata>/Statistics/, e.g., WorkbookStatistics_Accumulated.json. You can delete these files if you are not interested in this information, or you can set this property to false to disable the accumulation completely.</appdata>
Default Value	true
Property	Subscription
Attribute	subscription.broadcasting.pool.max.size
Description	The maximum number of threads for the broadcasting thread pools of refresh events.
	The default value is empty, which means that there is no limit. Any value less than 1 also means that there is no limit. When setting a max value for the thread pools, it means that the pool cannot create more than that number of threads. If there are more concurrent events handled by the thread pools than there are threads, they are queued until a thread becomes available.
	The thread pools are also configured to only increase the pool size if all threads are busy and a new event needs to be processed. If a thread is idle more than 1 minute, it will be removed from the pool and the size of the pool thereby decreases.
	Any subscription for a static data source are scheduled to refresh each X seconds (based of the refresh period of the datatable) using the TaskScheduled built in to Spring.
	If multiple subscriptions with the same data query tries to load data at the same time, only one thread will actually load the data. The rest of the subscriptions are queued. When the data is loaded all waiting subscriptions will be given the same data set that are then broadcasted to their respective client.
Default Value	
Property	Subscription
Attribute	subscription.compression.delta.enabled
Description	With delta compression, the server only sends the difference from the last data result on each refresh. For data where only a fraction changes on each refresh, this means much smaller response messages.

	The trade-offs are that both client and server need to keep the last result to calculate the difference and apply it, and that this operation takes some additional time both on the server and the client.				
	In rare cases, delta compression may worsen performance, e.g., if you have a large data set with very high refresh rate and a large portion of the data changes on each refresh. You can then disable delta processing completely by setting this property to false .				
Default Value	true				
Property	Subscription				
Attribute	subscription.compression.enabled				
Description	Enable or disable compression and encoding of subscription broadcast messages.				
Default Value	true				
Property	Subscription				
Attribute	subscription.congestion.control.enabled				
Description	When the server loads data for a subscription, it checks that the previous data load for it has completed. If not, it might be a sign that the refresh rate is set too high on the data table. If this happens subscription.maximum.failure times in a row, the server will cancel the subscription. Set this property to false to disable this behavior.				
Default Value	true				
Property	Subscription				
Attribute	subscription.data.loading.pool.max.size				
Description	The maximum number of threads for loading thread pools of refresh events. The default value is empty, which means that there is no limit. Any value less than 1 also means that there is no limit. When setting a max value for the thread pools, it means that the pool cannot create more than that number of threads. If there are more concurrent events handled by the thread pools than there are threads, they are queued until a thread becomes available. The thread pools are also configured to only increase the pool size if all threads are busy and a new event needs to be processed. If a thread is idle more than 1 minute, it will be removed from the pool and the size of the pool thereby decreases.				
	Any subscription for a static data source is scheduled to refresh each X seconds (based of the refresh period of the data table) using the TaskScheduled built into Spring.				
	If multiple subscriptions with the same data query tries to load data at the same time, only one thread will actually load the data. The rest of the subscriptions are queued. When the data is loaded all waiting subscriptions will be given the same data set that are then broadcasted to their respective client.				
Default Value					
Property	Subscription				
Attribute	subscription.data_log.always_on				
Description	When set to true , the data log is always passed from server to client if the user is a Designer or Admin on the server. Previously, the data log would only be passed for workbooks in design mode.				
	The data log will be passed also when the data request fails. The "Invalid Configuration" message shown in the visualization will show a "Data Log" button, which will display the relevant logs and error message.				

	NOTE: The actual passing of runtime exception is currently implemented in the Kdb+ connector only.				
	The benefit of running a server with subscription.data.log.always_on=true is that, the data log is more easily accessed and can be viewed both as success and failure. The data log can also be viewed without having Write permissions on the folder where the workbook is used, which is helpful when connection failures need to be examined in production environments where you have restrictions on workbook editing.				
	NOTE: Viewer users are not able to view the Data Log, only Designers and Admins.				
Default Value	false				
Property	Subscription				
Attribute	subscription.limitation.action				
Description	Controls the behavior when the subscription.limitation.limit is reached. Allowed values: EXCEPTION, PURGE				
Default Value	EXCEPTION				
Property	Subscription				
Attribute	subscription.limitation.enabled				
Description	Enables limitation of subscriptions.				
Default Value	false				
Property	Subscription				
Attribute	subscription.limitation.limit				
Description	Defines a subscription limit.				
Default Value	100				
Property	Subscription				
Attribute	subscription.log.slow.data.loads.seconds				
Description	Logs a subscription that has been loading data for more than X seconds at a WARNING level. NOTES: Any integer less than 1 (or an empty value) will disable the logging.				
	 If a slow data load has been logged and then returns data, a log message at INFO level will be printed stating that a previously logged slow data load has returned data. 				
Default Value	60				
Property	Subscription				
Attribute	subscription.maximum.failure				
Description	The amount of time a subscription is allowed to fail in a row before it should be cancelled. The number will be reset to zero if data loading is successful. The maximum failure limit is used so that invalid subscription will not loop forever and fill the logs with error messages. The value -1 will disable the fail mechanism. This means that a subscription can fail endless of times and not be cancelled.				
Default Value	5				
Property	Subscription				

Attribute	subscription.purge.condition				
Description	Defines the condition for when subscriptions will be purged. Allowed values: NONE, MEMORY				
Default Value	NONE				
Property	Subscription				
Attribute	subscription.purge.condition.memory.threshold				
Description	Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY.				
Default Value	80				
Property	Subscription				
Attribute	subscription.purge.enabled				
Description	Enables subscription purging.				
Default Value	true				
Property	Subscription				
Attribute	subscription.purge.post.restart				
Description	Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL				
Default Value	false				
Property	Subscription				
Attribute	subscription.purge.rate				
Description	Defines a fixed rate, in milliseconds. for subscription purging.				
Default Value	10000				
Property	Subscription				
Attribute	subscription.purge.scope				
Description	Defines the scope of subscriptions to purge. Allowed values: NON_PERSISTENT_ORPHANS, ALL.				
Default Value	NON_PERSISTENT_ORPHANS				
Property	Timeout Session				
Attribute	timeout.session.enabled				
Description	Boolean value stating if timeout functionality should be used or not.				
Default Value	false				
Property	Timeout Session				
Attribute	timeout.session.exception.delimiter				
Description	The delimiter to use for the usernames stated in the timeout.session.exception.usernames property.				
Default Value	, (comma)				

Property	Timeout Session				
Attribute	timeout.session.exception.usernames				
Description	Usernames that should be excluded from the timeout functionality. Separated by the delimiter stated in the timeout.session.exception.delimiter property.				
Default Value					
Property	Timeout Session				
Attribute	timeout.session.minutes				
Description	Minutes of inactivity before a user session is terminated by logging out the user.				
Default Value	480				
Property	Timeout Session				
Attribute	timeout.session.notification.minutes				
Description	Minutes before a timeout that a notification about session timeout is sent to the user.				
Default Value	1				
Property	WebSocket Connection				
Attribute	transport.buffer.size.max.bytes				
Description	Maximum size of message buffer for the WebSocket connections.				
Default Value	10000000				
Property	WebSocket Connection				
Attribute	transport.message.size.max.bytes				
Description	Maximum size of messages for the WebSocket connections.				
Default Value	1000000				

	10D	

For more information on Panopticon and other resources, go to https://www.altair.com/panopticon.